

Sentaurus™ Device Electromagnetic Wave Solver User Guide

Version N-2017.09, September 2017

SYNOPSYS®

Copyright and Proprietary Information Notice

©2017 Synopsys, Inc. This Synopsys software and all associated documentation are proprietary to Synopsys, Inc. and may only be used pursuant to the terms and conditions of a written license agreement with Synopsys, Inc. All other use, reproduction, modification, or distribution of the Synopsys software or the associated documentation is strictly prohibited.

Destination Control Statement

All technical data contained in this publication is subject to the export control laws of the United States of America. Disclosure to nationals of other countries contrary to United States law is prohibited. It is the reader's responsibility to determine the applicable regulations and to comply with them.

Disclaimer

SYNOPSYS, INC., AND ITS LICENSORS MAKE NO WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, WITH REGARD TO THIS MATERIAL, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE.

Trademarks

Synopsys and certain Synopsys product names are trademarks of Synopsys, as set forth at <https://www.synopsys.com/company/legal/trademarks-brands.html>. All other product or company names may be trademarks of their respective owners.

Third-Party Links

Any links to third-party websites included in this document are for your convenience only. Synopsys does not endorse and is not responsible for such websites and their practices, including privacy practices, availability, and content.

Synopsys, Inc.
690 E. Middlefield Road
Mountain View, CA 94043
www.synopsys.com

Contents

About This Guide	vii
Related Publications	vii
Conventions	vii
Customer Support	vii
Accessing SolvNet	viii
Contacting Synopsys Support	viii
Contacting Your Local TCAD Support Team Directly	viii
Acknowledgments	ix
<hr/>	
Chapter 1 Getting Started	1
Starting EMW	1
Input and Output File Types	2
Command File (*.eml.cmd)	2
Tensor-Grid File (*.msh.tdr)	3
Parameter File (*.eml.par)	4
Plot, Extractor, and Save Files (*.eml.tdr)	5
Result File (*.eml.plt)	5
Log Files (*.eml.log, *.eml.out)	5
File Compression	5
Accessing Help on Syntax	5
<hr/>	
Chapter 2 Basic Theory of Finite-Difference Time-Domain Method	7
Basic Theory of FDTD	7
Discretized Maxwell's Equations	7
Accuracy of the Finite Difference Stencil	11
Stability (Courant) Criteria	12
Modeling of Dispersive Media	12
Physical Model	13
Debye Relaxation	14
Lorentzian Resonance	14
Unmagnetized Plasma	15
Drude-Lorentz	15
Modified Lorentz	15
Drude-Modified Lorentz	16
References	16

Contents

Chapter 3 Boundary Conditions	19
Introduction	19
PEC and PMC Boundary Conditions	19
Periodic Boundary Conditions	19
Absorbing Boundary Conditions	20
Specifying Parameters of CPML Boundary Condition	21
Combining CPML With Other Boundary Conditions	23
References	24

Chapter 4 Building the Correct Mesh	25
Generating Tensor Meshes for EMW	25
Using the Sentaurus Mesh Tensor-Product Generator	25
Specifying Nodes per Wavelength in Meshing	26
Meshing Examples	27
Example 1: Planar Two-Layer Silicon–Air	28
Example 2: Image Sensor	29
Inspecting and Troubleshooting Tensor-Grid Generation	31

Chapter 5 Specifying Material Parameters	33
Introduction	33
Complex Refractive Index Model	33
Complex Refractive Index Model Interface	34
Spatially Dependent Complex Refractive Index Model	35
Limitations	36
Dispersive Model Parameters	37
Dispersive Model Command Syntax	37
Specifying User-Defined Dispersive Model Poles in Parameter File	39
Explicit Specification of EMW Material Parameters	42
PEC and PMC Materials	43
Precedence of Material Specification	44

Chapter 6 Specifying Excitations	45
Overview	45
Total-Field Scattered-Field	45
Plane Waves	46
Specifying Excitation Regions or Boxes	46
Specifying Direction and Polarization	47
Specifying Elliptical Polarization	49

Spatially Incoherent Illumination	50
Gaussian Beam or Gaussian Field Distribution	51
Temporal Dependency	53
CODE V Interface	55
References	57
<hr/>	
Chapter 7 Terminating Simulations	59
Options for Terminating FDTD Time-Stepping Loop	59
Detectors	60
<hr/>	
Chapter 8 Extracting and Visualizing Results	63
Overview	63
Plots	64
Monitors	67
Extractors	68
Sensors	70
Using Multiple Domains in a Sensor	72
Nonaxis-Aligned Sensor	73
Far Field	74
Specifying the Far-Field Computation	76
Visualizing Results of the Far-Field Computation	78
Postprocessing of Extractors, Sensors, and Far Field	80
Discrete Fourier Transform	82
On-the-Fly DFT	82
Defining the DFT Wavelength Table	83
Normalizing Field Values	84
Downsampling of DFT	85
Limitation of Single-Frequency Periodic Boundary Condition	85
EMW Syntax	86
References	88
<hr/>	
Chapter 9 Parallelization	89
Overview	89
Shared-Memory Parallelization	89
Parallelization of Message Passing Interface	90
Domain Decomposition	90
Installing and Using EMW MPI on DP Systems	91
Hardware and Software Setup	91
Licensing for SMP and DP Parallel Modes	91

Contents

Controlling Parallel Licenses	92
Installing Clusters	93
Running EMW MPI on a Cluster	93
Choosing Between Shared-Memory Parallelization and Distributed Processing	96
References	97
<hr/>	
Appendix A Commands	99
Boundary	99
CodeVExcitation	101
ComplexRefractiveIndex	102
Detector	103
DFT	105
DispersiveMedia	105
Extractor	106
Farfield	109
GaussianBeamExcitation	111
Globals	113
Monitor	115
PECMedia	116
PlaneWaveExcitation	117
Plot	119
PMCMedia	123
Save	123
Sensor	125
TruncatedPlaneWaveExcitation	128
<hr/>	
Appendix B Troubleshooting Simulations	131
Unexpected Results	131
Simulations Run Nonstop	132
Simulator Terminates	132
<hr/>	
Appendix C Message Passing Interface	133
Frequently Asked Questions	133
Can I Run EMW MPI Through Sentaurus Workbench?	133
Troubleshooting MPI	133
Verifying MPI Setup Is Correct	133
<hr/>	
Glossary	135

About This Guide

The Synopsys Sentaurus™ Device Electromagnetic Wave Solver (EMW) is a simulation module for the numeric analysis of electromagnetic waves. EMW is a full-wave time-domain simulator based on the finite-difference time-domain (FDTD) method. It is typically used to calculate the optical carrier generation in optoelectronic devices.

EMW can compute full-wave time-domain solutions of Maxwell equations, thereby covering the entire range of electromagnetic problems from high frequency to optical applications.

Related Publications

For additional information, see:

- The TCAD Sentaurus release notes, available on the Synopsys SolvNet® support site (see [Accessing SolvNet on page viii](#)).
- Documentation available on SolvNet at <https://solvnet.synopsys.com/DocsOnWeb>.

Conventions

The following conventions are used in Synopsys documentation.

Convention	Description
Blue text	Identifies a cross-reference (only on the screen).
Bold text	Identifies a selectable icon, button, menu, or tab. It also indicates the name of a field or an option.
Courier font	Identifies text that is displayed on the screen or that the user must type. It identifies the names of files, directories, paths, parameters, keywords, and variables.
<i>Italicized text</i>	Used for emphasis, the titles of books and journals, and non-English words. It also identifies components of an equation or a formula, a placeholder, or an identifier.

Customer Support

Customer support is available through the Synopsys SolvNet customer support website and by contacting the Synopsys support center.

Accessing SolvNet

The SolvNet support site includes an electronic knowledge base of technical articles and answers to frequently asked questions about Synopsys tools. The site also gives you access to a wide range of Synopsys online services, which include downloading software, viewing documentation, and entering a call to the Support Center.

To access the SolvNet site:

1. Go to the web page at <https://solvnet.synopsys.com>.
2. If prompted, enter your user name and password. (If you do not have a Synopsys user name and password, follow the instructions to register.)

If you need help using the site, click **Help** on the menu bar.

Contacting Synopsys Support

If you have problems, questions, or suggestions, you can contact Synopsys support in the following ways:

- Go to the Synopsys [Global Support Centers](#) site on synopsys.com. There you can find e-mail addresses and telephone numbers for Synopsys support centers throughout the world.
 - Go to either the Synopsys SolvNet site or the Synopsys Global Support Centers site and [open a case online](#) (Synopsys user name and password required).
-

Contacting Your Local TCAD Support Team Directly

Send an e-mail message to:

- support-tcad-us@synopsys.com from within North America and South America.
- support-tcad-eu@synopsys.com from within Europe.
- support-tcad-ap@synopsys.com from within Asia Pacific (China, Taiwan, Singapore, Malaysia, India, Australia).
- support-tcad-kr@synopsys.com from Korea.
- support-tcad-jp@synopsys.com from Japan.

Acknowledgments

The TCAD Sentaurus software uses the MPICH message passing interface (MPI) package, which requires the following copyright notice:

Copyright Notice
+ 2002 University of Chicago

Permission is hereby granted to use, reproduce, prepare derivative works, and to redistribute to others. This software was authored by:

Mathematics and Computer Science Division
Argonne National Laboratory, Argonne IL 60439

(and)

Department of Computer Science
University of Illinois at Urbana-Champaign

GOVERNMENT LICENSE

Portions of this material resulted from work developed under a U.S. Government Contract and are subject to the following license: the Government is granted for itself and others acting on its behalf a paid-up, nonexclusive, irrevocable worldwide license in this computer software to reproduce, prepare derivative works, and perform publicly and display publicly.

DISCLAIMER

This computer code material was prepared, in part, as an account of work sponsored by an agency of the United States Government. Neither the United States, nor the University of Chicago, nor any of their employees, makes any warranty express or implied, or assumes any legal liability or responsibility for the accuracy, completeness, or usefulness of any information, apparatus, product, or process disclosed, or represents that its use would not infringe privately owned rights.

About This Guide
Acknowledgments

CHAPTER 1 Getting Started

This chapter describes the Sentaurus Device Electromagnetic Wave Solver application, how to set up simulations, and the general syntax framework.

Starting EMW

Sentaurus Device Electromagnetic Wave Solver (EMW) is an electromagnetic solver based on the finite-difference time-domain (FDTD) method. It can numerically solve the temporal evolution of electromagnetic waves in a device structure defined on a tensor grid. The main result is the absorbed photon density distribution, which is typically used in subsequent electrical simulations.

To start EMW from the command line, use:

```
> emw [command_file_name]
```

where the optional `command_file_name` is a valid command file of EMW, for example:

```
> emw pp1_eml.cmd
```

To list the command-line options, use:

```
> emw -h
```

To list all of the installed EMW releases, use:

```
> emw -releases
```

To check the default version number, use:

```
> emw -v
```

To run a particular release version, use:

```
> emw -rel M-2016.12
```

Input and Output File Types

The main input and output file types used in EMW simulations are shown in [Figure 1](#). The file names can be specified in the EMW command file.




Figure 1 Overview of input and output files for EMW

Command File (*_eml.cmd)

The command file is the main input file for EMW. It contains all the model settings and file specifications, and can be edited. This file is referred to as the *command file* or *input file*.

An EMW command file consists of several command sections of the form `Section {...}`, with each section describing a specific aspect of the simulation. Inside a section, each command keyword has the form `keyword = value`, for example:

```
* Plot the absolute value of the electric field at the end of the simulation
Plot {
  Name      = "n@node@_Eabs"
  Quantity  = {AbsElectricField, AbsMagneticField, Region}
  TickStep  = 300
  StartTick = 100
  EndTick   = 800
  FinalPlot = yes
}
```

NOTE Regarding the command file:

- Keywords are case insensitive, but identifiers such as region names and materials are surrounded by double quotation marks and are case sensitive.
- Lists are defined in braces with their items separated by a comma.
- Each command must be on a single line; only list items can be wrapped before or after the comma.
- Comments are indicated by the first character on a line being # or *.

Typically, an EMW command file consists of the following sections:

- Globals
- ComplexRefractiveIndex
- DispersiveMedia
- Boundary
- PlaneWaveExcitation
- Plot
- Extractor
- Sensor
- Monitor
- Detector

In general, the order of the sections in the command file is arbitrary. However, it is recommended that you maintain the above order because it simplifies navigation looking for a particular parameter.

Tensor-Grid File (*_msh.tdr)

EMW needs a tensor grid to run FDTD simulations. A typical example of a tensor grid is shown in [Figure 2 on page 4](#). To generate a suitable tensor-grid file with Sentaurus Mesh, see [Generating Tensor Meshes for EMW on page 25](#) and the *Sentaurus™ Mesh User Guide*.

1: Getting Started

Input and Output File Types




Figure 2 Example of a tensor grid of a CMOS image sensor; oxide removed for visualization

Parameter File (*_eml.par)

EMW allows you to define the optical parameters as a complex refractive index (CRI) in the material parameter file. It uses the same CRI library as Sentaurus Device. Therefore, the same parameter file as for Sentaurus Device can be used (refer to the *Sentaurus™ Device User Guide*).

The optical parameters are then read from the corresponding `ComplexRefractiveIndex` section, for example:

```
Material = "Silicon" {
  ComplexRefractiveIndex {
    Formula = 1
    NumericalTable (
      0.1908  0.84  2.73;
      ...
    )
  }
}
```

Plot, Extractor, and Save Files (*_eml.tdr)

As multiple `Plot`, `Extractor`, and `Save` sections are allowed, the file names are defined in the corresponding sections. Extracting useful simulation results is described in more detail in [Chapter 8 on page 63](#).

Result File (*_eml.plt)

A result file is used when global values have to be stored, such as the integrated absorbed photon density in a certain volume or the photon flux through a surface. The results can be viewed using `Inspect` or `Sentaurus Visual`. For discrete Fourier transform (DFT) simulations, use `Sentaurus Visual` only.

Log Files (*_eml.log, *_eml.out)

EMW generates the log file during a simulation run. It contains information about input parameters, and the models and values of physical parameters used in the simulation. The log file contains more details than the brief information written to the standard output (`.out`) during the simulation.

File Compression

You can control further compression, beyond a basic standard compression for plot, sensor, extractor, and save files as well as the result file, in the `Globals` section by specifying `CompressTDR=Yes | No`.

Accessing Help on Syntax

Help for the syntax of each keyword can be obtained by using the EMW binary with the `-P` command-line option. For example, to view all of the allowed options for the keyword `Quantity` in the `Plot` section, in a shell, type in a shell prompt:

```
> emw -P:plot:quantity
*****
***                               Sentaurus Device EMW                               ***
...
Quantity = { <identifier>, ... }
  Default value: { AbsElectricField }
```

1: Getting Started

Accessing Help on Syntax

```
Exclusive options are: AbsElectricDisplacement  
AbsElectricField
```

...

CHAPTER 2 Basic Theory of Finite-Difference Time-Domain Method

This chapter describes the basic theory of the finite-difference time-domain (FDTD) method, including the total-field scattered-field methodology and the dispersive material models.

Basic Theory of FDTD

EMW provides a FDTD kernel that specifically targets 3D periodic structures for which light is incident at an oblique angle. Typically, periodic boundary conditions must be imposed in the lateral directions; whereas, absorbing boundary conditions are applied in the normal direction. The implementation of the kernel is based on the sine–cosine formulation [1][2] and can be applied to both coherent and incoherent excitations. Prominent application areas for the FDTD kernel with 3D oblique periodic boundary conditions are CMOS image sensors, solar cells, and photonic bandgap structures.

NOTE The sine–cosine formulation is based on two sets of field components, one with sine and one with cosine time dependency, which are advanced simultaneously in time. Therefore, the memory footprint of this method is, at least, doubled compared to the conventional FDTD algorithm.

NOTE Two-dimensional simulations using the 3D FDTD kernel with oblique periodic boundary conditions are performed by extruding the 2D structure by one layer in the third dimension.

Discretized Maxwell's Equations

Maxwell's curl equations in linear, isotropic, nondispersive material are [1]:

$$\begin{aligned}\frac{\partial \mathbf{E}}{\partial t} &= \frac{1}{\epsilon} \nabla \times \mathbf{H} - \frac{1}{\epsilon} (\mathbf{J} + \sigma \mathbf{E}) \\ \frac{\partial \mathbf{H}}{\partial t} &= -\frac{1}{\mu} \nabla \times \mathbf{E} - \frac{1}{\mu} (\mathbf{M} + \sigma^* \mathbf{H})\end{aligned}\tag{1}$$

2: Basic Theory of Finite-Difference Time-Domain Method

Basic Theory of FDTD

where:

- \mathbf{E} is the vectorial electric field in V/m .
- \mathbf{H} is the vectorial magnetic field in A/m .
- \mathbf{J} is the electric current density in A/m² .
- \mathbf{M} is the magnetic current density in V/m² .
- ϵ is the electrical permittivity in F/m .
- μ is the magnetic permeability in H/m .
- σ is the electric conductivity in S/m .
- σ^* is the magnetic conductivity in Ω /m .

In terms of x-, y-, and z-components, the curl equations can be decomposed into a system of six coupled scalar equations:

$$\begin{aligned}\frac{\partial E_x}{\partial t} &= \frac{1}{\epsilon} \left[\frac{\partial H_z}{\partial y} - \frac{\partial H_y}{\partial z} - (J_x + \sigma E_x) \right] \\ \frac{\partial E_y}{\partial t} &= \frac{1}{\epsilon} \left[\frac{\partial H_x}{\partial z} - \frac{\partial H_z}{\partial x} - (J_y + \sigma E_y) \right] \\ \frac{\partial E_z}{\partial t} &= \frac{1}{\epsilon} \left[\frac{\partial H_y}{\partial x} - \frac{\partial H_x}{\partial y} - (J_z + \sigma E_z) \right] \\ \frac{\partial H_x}{\partial t} &= \frac{1}{\mu} \left[\frac{\partial E_y}{\partial z} - \frac{\partial E_z}{\partial y} - (M_x + \sigma^* H_x) \right] \\ \frac{\partial H_y}{\partial t} &= \frac{1}{\mu} \left[\frac{\partial E_z}{\partial x} - \frac{\partial E_x}{\partial z} - (M_y + \sigma^* H_y) \right] \\ \frac{\partial H_z}{\partial t} &= \frac{1}{\mu} \left[\frac{\partial E_x}{\partial y} - \frac{\partial E_y}{\partial x} - (M_z + \sigma^* H_z) \right]\end{aligned}\tag{2}$$

Maxwell's curl equations can be discretized by the central difference method to achieve second-order accuracy. For nonuniform grids with $\Delta x \neq \Delta y \neq \Delta z$, the discretized x-, y-, and z-components of the E-fields for the point (i, j, k) are:

$$\begin{aligned}
 E_x \Big|_{i+\frac{1}{2},j,k}^{n+1} &= C_{a,E_x} \Big|_{i+\frac{1}{2},j,k} E_x \Big|_{i+\frac{1}{2},j,k}^n \\
 &+ C_{b,E_x} \Big|_{i+\frac{1}{2},j,k} \left[\left(H_z \Big|_{i+\frac{1}{2},j+\frac{1}{2},k}^{n+\frac{1}{2}} - H_z \Big|_{i+\frac{1}{2},j-\frac{1}{2},k}^{n+\frac{1}{2}} \right) / \Delta y \right. \\
 &- \left. \left(H_y \Big|_{i+\frac{1}{2},j,k+\frac{1}{2}}^{n+\frac{1}{2}} - H_y \Big|_{i+\frac{1}{2},j,k-\frac{1}{2}}^{n+\frac{1}{2}} \right) / \Delta z \right. \\
 &- \left. J_x \Big|_{i+\frac{1}{2},j,k}^{n+\frac{1}{2}} \right]
 \end{aligned} \tag{3}$$

$$\begin{aligned}
 E_y \Big|_{i,j+\frac{1}{2},k}^{n+1} &= C_{a,E_y} \Big|_{i,j+\frac{1}{2},k} E_y \Big|_{i,j+\frac{1}{2},k}^n \\
 &+ C_{b,E_y} \Big|_{i,j+\frac{1}{2},k} \left[\left(H_x \Big|_{i,j+\frac{1}{2},k+\frac{1}{2}}^{n+\frac{1}{2}} - H_x \Big|_{i,j+\frac{1}{2},k-\frac{1}{2}}^{n+\frac{1}{2}} \right) / \Delta z \right. \\
 &- \left. \left(H_z \Big|_{i+\frac{1}{2},j+\frac{1}{2},k}^{n+\frac{1}{2}} - H_z \Big|_{i-\frac{1}{2},j+\frac{1}{2},k}^{n+\frac{1}{2}} \right) / \Delta x \right. \\
 &- \left. J_y \Big|_{i,j+\frac{1}{2},k}^{n+\frac{1}{2}} \right]
 \end{aligned} \tag{4}$$

$$\begin{aligned}
 E_z \Big|_{i,j,k+\frac{1}{2}}^{n+1} &= C_{a,E_z} \Big|_{i,j,k+\frac{1}{2}} E_z \Big|_{i,j,k+\frac{1}{2}}^n \\
 &+ C_{b,E_z} \Big|_{i,j,k+\frac{1}{2}} \left[\left(H_y \Big|_{i+\frac{1}{2},j,k+\frac{1}{2}}^{n+\frac{1}{2}} - H_y \Big|_{i-\frac{1}{2},j,k+\frac{1}{2}}^{n+\frac{1}{2}} \right) / \Delta x \right. \\
 &- \left. \left(H_x \Big|_{i,j+\frac{1}{2},k+\frac{1}{2}}^{n+\frac{1}{2}} - H_x \Big|_{i,j-\frac{1}{2},k+\frac{1}{2}}^{n+\frac{1}{2}} \right) / \Delta y \right. \\
 &- \left. J_z \Big|_{i,j,k+\frac{1}{2}}^{n+\frac{1}{2}} \right]
 \end{aligned} \tag{5}$$

2: Basic Theory of Finite-Difference Time-Domain Method

Basic Theory of FDTD

where:

$$C_{a,\gamma}|_{i,j,k} = \left(1 - \frac{\sigma_{i,j,k}\Delta t}{2\varepsilon_{i,j,k}}\right) / \left(1 + \frac{\sigma_{i,j,k}\Delta t}{2\varepsilon_{i,j,k}}\right), \quad \gamma = E_x, E_y, E_z \quad (6)$$

$$C_{b,\gamma}|_{i,j,k} = \left(\frac{\Delta t}{\varepsilon_{i,j,k}}\right) / \left(1 + \frac{\sigma_{i,j,k}\Delta t}{2\varepsilon_{i,j,k}}\right), \quad \gamma = E_x, E_y, E_z$$

The discretized x-, y-, and z-components of the H-fields for the point (i, j, k) are:

$$H_x|_{i,j+\frac{1}{2},k+\frac{1}{2}}^{n+\frac{1}{2}} = D_{a,H_x}|_{i,j+\frac{1}{2},k+\frac{1}{2}} H_x|_{i,j+\frac{1}{2},k+\frac{1}{2}}^{n-\frac{1}{2}} + D_{b,H_x}|_{i,j+\frac{1}{2},k+\frac{1}{2}} \left[\left(E_y|_{i,j+\frac{1}{2},k+1}^n - E_y|_{i,j+\frac{1}{2},k}^n \right) / \Delta z - \left(E_z|_{i,j+1,k+\frac{1}{2}}^n - E_z|_{i,j,k+\frac{1}{2}}^n \right) / \Delta y - M_x|_{i,j+\frac{1}{2},k+\frac{1}{2}}^n \right] \quad (7)$$

$$H_y|_{i+\frac{1}{2},j,k+\frac{1}{2}}^{n+\frac{1}{2}} = D_{a,H_y}|_{i+\frac{1}{2},j,k+\frac{1}{2}} H_y|_{i+\frac{1}{2},j,k+\frac{1}{2}}^{n-\frac{1}{2}} + D_{b,H_y}|_{i+\frac{1}{2},j,k+\frac{1}{2}} \left[\left(E_z|_{i+1,j,k+\frac{1}{2}}^n - E_z|_{i,j,k+\frac{1}{2}}^n \right) / \Delta x - \left(E_x|_{i+\frac{1}{2},j,k+1}^n - E_x|_{i+\frac{1}{2},j,k}^n \right) / \Delta z - M_y|_{i+\frac{1}{2},j,k+\frac{1}{2}}^n \right] \quad (8)$$

$$\begin{aligned}
 H_z \Big|_{i+\frac{1}{2}, j+\frac{1}{2}, k}^{n+\frac{1}{2}} &= D_{a, H_z} \Big|_{i+\frac{1}{2}, j+\frac{1}{2}, k} H_z \Big|_{i+\frac{1}{2}, j+\frac{1}{2}, k}^{n-\frac{1}{2}} \\
 &+ D_{b, H_z} \Big|_{i+\frac{1}{2}, j+\frac{1}{2}, k} \left[\left(E_x \Big|_{i+\frac{1}{2}, j+1, k}^n - E_x \Big|_{i+\frac{1}{2}, j, k}^n \right) / \Delta y \right. \\
 &- \left. \left(E_y \Big|_{i+1, j+\frac{1}{2}, k}^n - E_y \Big|_{i, j+\frac{1}{2}, k}^n \right) / \Delta x \right. \\
 &- \left. M_z \Big|_{i+\frac{1}{2}, j+\frac{1}{2}, k}^n \right]
 \end{aligned} \tag{9}$$

where:

$$\begin{aligned}
 D_{a, \gamma} \Big|_{i, j, k} &= \left(1 - \frac{\sigma_{i, j, k}^* \Delta t}{2\mu_{i, j, k}} \right) / \left(1 + \frac{\sigma_{i, j, k}^* \Delta t}{2\mu_{i, j, k}} \right), \quad \gamma = H_x, H_y, H_z \\
 D_{b, \gamma} \Big|_{i, j, k} &= \left(\frac{\Delta t}{\mu_{i, j, k}} \right) / \left(1 + \frac{\sigma_{i, j, k}^* \Delta t}{2\mu_{i, j, k}} \right), \quad \gamma = H_x, H_y, H_z
 \end{aligned} \tag{10}$$

In the above equations, Δt is the time step and it must satisfy the [Stability \(Courant\) Criteria](#).

NOTE Magnetic material is not supported, that is, $\mu = \mu_0$ and $\sigma^* = 0$ in [Eq. 1, p. 7](#) and the corresponding equations. Here, μ_0 denotes the vacuum magnetic permeability.

Accuracy of the Finite Difference Stencil

The accuracy of the finite difference stencil critically depends on cell size and mesh uniformity. For a uniform tensor mesh, the Yee algorithm [3] is second-order accurate for both time and spatial discretization. However, the accuracy will degrade if the mesh is nonuniform, because the numeric dispersion of the finite difference method increases when the cells have large aspect ratios or abrupt grading or both.

NOTE Whenever an FDTD simulation has slow convergence or unstable results, first check whether convergence and stability can be improved by using a denser uniform mesh for the same problem.

Stability (Courant) Criteria

The explicit FDTD-updating algorithm initially proposed by Yee [3] is conditionally stable, which means that there is an upper limit to the allowed time step for stable operation:

$$\Delta t \leq \Delta t_{\text{stable}} \quad (11)$$

Time steps that are greater than Δt_{stable} cause exponentially growing solutions. The theoretical proof of the stability criterion is usually given for the linear case on uniform grids, derived by examining how a plane wave is impacted by the FDTD discretized stencil. However, numeric experiments have shown that the following selection of Δt is also satisfactory for rectilinear (nonuniform) grids and in combination with the commonly used boundary conditions:

$$\text{3D case: } \Delta t_{\text{stable}} = \frac{1}{v \sqrt{\frac{1}{(\Delta x)^2} + \frac{1}{(\Delta y)^2} + \frac{1}{(\Delta z)^2}}} \quad (12)$$

$$\text{2D case: } \Delta t_{\text{stable}} = \frac{1}{v \sqrt{\frac{1}{(\Delta x)^2} + \frac{1}{(\Delta y)^2}}} \quad (13)$$

where v denotes the phase velocity of the wave, and Δx , Δy , and Δz are the space increments of the grid.

NOTE In the case of a rectilinear grid, the smallest space increments of the grid must be used in Eq. 12 and Eq. 13.

Modeling of Dispersive Media

In the derivation of the FDTD-updating scheme, which forms the basis of EMW, it is generally assumed that the material parameters ϵ , μ , σ , and σ_m are independent of frequency. As long as interest is restricted to model situations with quasimonochromatic excitation, the formulations in the previous sections are sufficient. However, the electromagnetic parameters of most materials generally exhibit a dependency on frequency that may be pronounced, especially in the range of visible wavelengths and frequencies.

If the excitation signal has a spectrum that is nonzero over a range of frequencies in which the material properties change significantly, the dispersive behavior must be taken into account in the simulation. In addition, for a highly absorbing material that has a complex refractive index $n + i\kappa$ such that $\kappa > n$ (especially true for some metals), the real part of the dielectric constant $\text{Re}[\epsilon_r] = n^2 - \kappa^2$ becomes negative and will result in instabilities when the nondispersive FDTD is used. This problem can be solved by treating the material as dispersive.

Various approaches for taking frequency-dependent material parameters into account in FDTD have emerged [1]. Adequate treatment of material dispersion is important for simulating the propagation of short pulses as well as for efficient modeling of propagation phenomena over a wide range of frequencies in the optical and microwave regimes. The common methods are based on three main principles:

- The z-transformation of Maxwell's curl equations.
- The solution of auxiliary differential equations (ADEs) between the electric displacement density and the polarization.
- The recursive computation of the convolution integrals between the electric field and the time-domain susceptibility.

Numerous investigations have shown that the ADE method offers very good accuracy and stability with moderate computational effort. In addition, it is very flexible with respect to the modeling of common types of dispersive material.

NOTE Only the ADE method is used in EMW.

Since the majority of materials of interest for various applications is not magnetically dispersive, EMW is restricted to the modeling of frequency-dependent electric materials.

Physical Model

If the electric permittivity depends on the frequency, the constitutive relation between the electric field and the displacement density becomes:

$$\bar{D}(\omega) = \varepsilon(\omega)\bar{E}(\omega) = \varepsilon_0\varepsilon_\infty\bar{E}(\omega) + \bar{P}(\omega) = \varepsilon_0[\varepsilon_\infty + \chi(\omega)]\bar{E}(\omega) \quad (14)$$

where:

- $\varepsilon(\omega)$ is the permittivity (generally a complex quantity).
- $\bar{P} = \varepsilon_0\chi(\omega)\bar{E}(\omega)$ is the electric polarization.
- $\chi(\omega) = \varepsilon(\omega)/\varepsilon_0 - \varepsilon_\infty$ is the electric susceptibility.

The frequency dispersive characteristics can be fully described by the electric susceptibility. The actual form of the susceptibility depends on the microscopic properties of the material.

Next is an overview of the common types of dispersive material model encountered in electromagnetics.

2: Basic Theory of Finite-Difference Time-Domain Method

Basic Theory of FDTD

Debye Relaxation

The Debye dispersive model describes the relaxation behavior of water molecules. Therefore, this dispersive type plays an important role in modeling electromagnetic polarization in biological tissues. The susceptibility of a multiterm Debye dispersive medium is given by:

$$\chi(\omega) = \sum_{p=1}^{N_p^{\text{Debye}}} \frac{\Delta\epsilon_p}{1 - i\omega\tau_p} \quad (15)$$

where:

- N_p^{Debye} denotes the number of Debye poles.
- $\Delta\epsilon_p = (\epsilon_s - \epsilon_\infty)A_p$ is the change in the relative permittivity due to the p^{th} pole.
- A_p is the amplitude.
- τ_p is the pole relaxation time.

Lorentzian Resonance

The Lorentzian dispersive model adequately describes the frequency-dependent response caused by damped oscillation of bounded electrons due to the applied external fields, and it is typically used for modeling semiconductors and insulators.

The susceptibility of a multiterm Lorentzian dispersive medium is given by:

$$\chi(\omega) = \sum_{p=1}^{N_p^{\text{Lorentz}}} \frac{\Delta\epsilon_p \omega_p^2}{\omega_p^2 - 2i\omega\delta_p - \omega^2} \quad (16)$$

where:

- N_p^{Lorentz} denotes the number of Lorentzian pole pairs.
- $\Delta\epsilon_p = (\epsilon_s - \epsilon_\infty)A_p$ is the change in the relative permittivity due to the p^{th} pole pair.
- A_p is the amplitude.
- ω_p is the undamped frequency of the p^{th} pole pair, and δ_p is its damping factor.

Unmagnetized Plasma

The Drude dispersive model describes the behavior that is exhibited by free electrons in metals. The susceptibility of a multiterm Drude medium is given by:

$$\chi(\omega) = - \sum_{p=1}^{N_p^{\text{Drude}}} \frac{\omega_p^2}{\omega^2 + i\omega\gamma_p} \quad (17)$$

where:

- N_p^{Drude} denotes the number of Drude poles.
- ω_p is the Drude pole frequency.
- γ_p is the inverse of the pole relaxation time or Drude damping factor.

Drude–Lorentz

For modeling certain semiconductors and metals with higher accuracy, you can combine the Lorentz and Drude models to characterize dispersive media over a wide frequency range [4]. The susceptibility of a multiterm Drude–Lorentz medium is given by:

$$\chi(\omega) = \sum_{p=1}^{N_p^{\text{Lorentz}}} \frac{\Delta\epsilon_p \omega_p^2}{\omega_p^2 - 2i\omega\delta_p - \omega^2} - \sum_{p=1}^{N_p^{\text{Drude}}} \frac{\omega_p^2}{\omega^2 + i\omega\gamma_p} \quad (18)$$

where the dispersive parameters are defined as in [Eq. 16](#) and [Eq. 17](#).

Modified Lorentz

Another effective dispersive model for semiconductors and metals is the modified Lorentz model. This model offers a better description of the dielectric function of silicon, aluminum, silver, and gold in the visible wavelength range, although the parameters in this model do not necessarily have a physical meaning [5][6]. The susceptibility of a multiterm modified-Lorentz medium is given by:

$$\chi(\omega) = \sum_{p=1}^{N_p^{\text{ModLorentz}}} \frac{\Delta\epsilon_p (\omega_p^2 - i\omega\delta_p')}{\omega_p^2 - 2i\omega\delta_p - \omega^2} \quad (19)$$

Compared with the Lorentz model in [Eq. 16, p. 14](#), δ_p' in the numerator is an additional damping factor that describes the direct polarization of the dispersive medium by the time derivative of the applied electric field [Eq. 19](#).

2: Basic Theory of Finite-Difference Time-Domain Method

References

Drude–Modified Lorentz

The Drude model can be combined with the modified Lorentz model to form the Drude–modified Lorentz model. The susceptibility of a multiterm Drude–modified Lorentz medium is given by:

$$\chi(\omega) = \sum_{p=1}^{N_p^{\text{ModLorentz}}} \frac{\Delta\epsilon_p(\omega_p^2 - i\omega\delta_p')}{\omega_p^2 - 2i\omega\delta_p - \omega^2} - \sum_{p=1}^{N_p^{\text{Drude}}} \frac{\omega_p^2}{\omega^2 + i\omega\gamma_p} \quad (20)$$

where the dispersive parameters are defined as in [Eq. 17, p. 15](#).

The formulations of the ADEs and associated convolutional perfectly matching layers (CPMLs) of the above dispersive materials have been detailed in [\[1\]](#).

NOTE Caution: Dispersive materials can be attached only to CPMLs, not to analytic absorbing boundaries. The physics and derivation of the above dispersive models are available in the literature [\[4\]\[7\]](#).

The syntax for activating the dispersive models is described in [Dispersive Model Parameters on page 37](#).

References

- [1] A. Taflove and S. C. Hagness, *Computational Electrodynamics: The Finite-Difference Time-Domain Method*, Boston: Artech House, 3rd ed., 2005.
- [2] P. Harms, R. Mittra, and W. Ko, “Implementation of the Periodic Boundary Condition in the Finite-Difference Time-Domain Algorithm for FSS Structures,” *IEEE Transactions on Antennas and Propagation*, vol. 42, no. 9, pp. 1317–1324, 1994.
- [3] K. S. Yee, “Numerical Solution of Initial Boundary Value Problems Involving Maxwell’s Equations in Isotropic Media,” *IEEE Transactions on Antennas and Propagation*, vol. AP-14, no. 3, pp. 302–307, 1966.
- [4] *Handbook of Optical Constants of Solids III*, E. D. Palik (ed.), San Diego: Academic Press, 1998.
- [5] A. Deinega and S. John, “Effective optical response of silicon to sunlight in the finite-difference time-domain method,” *Optics Letters*, vol. 37, no. 1, pp. 112–114, 2012.

- [6] A. Vial *et al.*, “A new model of dispersion for metals leading to a more accurate modeling of plasmonic structures using the FDTD method,” *Applied Physics A*, vol. 103, no. 3, pp. 849–853, 2011.
- [7] M. Dressel and G. Grüner, *Electrodynamics of Solids: Optical Properties of Electrons in Matter*, Cambridge: Cambridge University Press, 2002.

2: Basic Theory of Finite-Difference Time-Domain Method

References

CHAPTER 3 **Boundary Conditions**

This chapter describes the boundary conditions that can be set up in Sentaurus Device Electromagnetic Wave Solver (EMW).

Introduction

Setting the right boundary conditions and the corresponding parameters, if required by the specific type of boundary condition, can play a crucial role in the quality of the simulation results.

The typical simulation setup for CMOS image sensor (CIS) and solar-cell applications is a normal or an oblique incident plane wave with periodic boundary conditions (BCs) at the sides and absorbing BCs at the top and bottom of the structure. Periodic BCs at the sides are inherent to the sine-cosine formulation [1] and require no additional configuration parameters to be set by the user. Absorbing BCs are discussed here.

PEC and PMC Boundary Conditions

Perfect electric conductor (PEC) and perfect magnetic conductor (PMC) boundary conditions are defined as BCs with zero tangential components of E- and H-fields, respectively.

An example of specifying PEC boundary conditions at the terminating sides in the x-direction is:

```
Boundary {  
    Type = PEC  
    Sides = {X}  
}
```

Periodic Boundary Conditions

Two types of periodic boundary condition are available:

- Periodic BC for normal incidence (`periodic`)
- Periodic BC for oblique incidence (`periodicoblique`)

3: Boundary Conditions

Absorbing Boundary Conditions

The `periodic` BC applies to plane wave excitations with normal incidence. The E- and H-fields are copied directly from one periodic facet to the opposing one during field update. Since only real fields are updated in the FDTD loop, the simulation is faster than the sine-cosine method [1], where both the real and imaginary fields must be updated.

The `periodicoblique` BC applies to plane wave excitations with both normal and oblique incidence. The E- and H-fields are updated by the sine-cosine method at periodic boundaries with a phase shift that depends on the incident angle.

NOTE For stability reasons, the use of the `periodicoblique` BC is recommended even for plane wave excitation with normal incidence.

Absorbing Boundary Conditions

Three types of absorbing boundary condition are available:

- Mur (`Mur`)
- Higdon (`Higdon`)
- Convolutional perfectly matched layer (CPML) (`CPML`)

Mur and Higdon BCs are computationally less costly than CPML BCs and do not require the specification of further-tuning parameters. Usually, the Higdon BC absorbs traveling waves incident on the boundary better than the Mur BC.

The most advanced absorbing BC is the CPML [2]. It generally gives the best results and can absorb waves impinging the boundary with a wide range of incidence angles. However, its quality depends on the choice of configuration parameters and it comes at a higher computational cost.

NOTE For sine-cosine simulation with large incident angles, it is preferable to use CPML to eliminate unwanted angle-dependent scatterings of the simulation results.

Absorbing boundaries and CPMLs can be placed on all sides of the simulation domain. This is useful for studying the scattering from a standalone structure instead of an array of structures. However, you cannot adjoin Mur and Higdon absorbing boundary conditions to CPMLs. Either all external boundaries are CPMLs or all external boundaries are Mur or Higdon absorbing BCs.

An example of specifying 25-layer CPMLs for all sides is:

```
Boundary {  
  Type = CPML  
  Sides = {X, Y, Z}  
  ...  
}
```

```
    Thickness = 25  
}
```

Specifying Parameters of CPML Boundary Condition

The CPML BC is configured with three different parameter profiles, σ , κ , and α , which determine the properties of each CPML. The number of layers can be specified independently for each side by setting the keyword `Thickness` to the corresponding integer value. The actual thickness of each CPML is predetermined by the tensor cell-size adjacent to the respective boundary. The two options of specifying the parameter profiles are either explicitly or by defining a polynomial grading.

For example, the σ profile of a five-layer CPML boundary at the bottom can be explicitly specified in the command file by using:

```
Boundary {  
    Type = CPML  
    Sides = {Zmin}  
    Thickness = 5  
    SigmaProfile = {0.003, 0.04, 0.09, 0.12, 0.18, 0.27, 0.49, 0.78, 0.92, 1.57}  
    ...  
}
```

The other profiles can be specified accordingly.

NOTE The number of values listed for each profile must be twice the number of CPMLs. The first value is assigned to the boundary interface, the second value is located half a cell into the CPML boundary, and so on. This is due to the staggered nature of the FDTD grid.

In the second option of polynomial grading, only two parameters for each profile must be specified: a maximum value and an exponent that determines how fast the value increases to its maximum within the CPML boundary. This is shown in the following command file excerpt:

```
Boundary {  
    Type = CPML  
    Sides = {Zmax}  
    Thickness = 15  
    SigmaMax = 4.3e5      # unit: 1/(Ohm*m), for 20 nm cell size  
    OrderSigma = 3  
    KappaMax = 1.  
    OrderKappa = 1  
    AlphaMax = 0
```

3: Boundary Conditions

Absorbing Boundary Conditions

```
OrderAlpha = 1
...
}
```

If the same parameters are to be used for both the lower boundary and the upper boundary in one coordinate direction, the keyword `Sides` can simply be set to `Z` in the above example.

By default, values are taken as specified in [2]:

Keyword	Default value
AlphaMax	0.2
KappaMax	15
OrderAlpha	1
OrderKappa	3
OrderSigma	3
SigmaMax	σ_{opt}
Thickness	15

where σ_{opt} depends on the cell size and the refractive index of the neighboring region. It is calculated for each boundary individually:

$$\sigma_{\text{opt}} = \frac{0.8(m+1)}{n\Delta Z_0} \quad (21)$$

where:

- m is the value of `OrderSigma`.
- n is the refractive index.
- Δ is the cell size of the neighboring cell.
- Z_0 is the vacuum impedance.

According to [2], this choice of σ_{opt} has proven to be relatively robust for many applications.

If the CPML quality needs to be improved, you can:

- Increase `Thickness` by a factor of two.
- Change `SigmaMax` by up to 50%.
- Change `AlphaMax` by up to 100%.

For more details on performance tuning of the CPML, refer to [2].

Combining CPML With Other Boundary Conditions

The CPML boundary condition can be combined with other types of boundary condition to suit various applications. [Table 1](#) and [Table 2](#) list the possible combinations for 2D and 3D simulations, respectively.

NOTE For [Table 1](#), x_1, x_2 can be either x, y or y, x . For [Table 2](#), x_1, x_2, x_3 can be either x, y, z or y, z, x or z, x, y .

Table 1 Boundary condition combinations with CPML in two dimensions

$x_{1,min}$	$x_{1,max}$	$x_{2,min}$	$x_{2,max}$
PeriodicOblique	PeriodicOblique	CPML	CPML
Periodic	Periodic	CPML	CPML
PEC	PEC	CPML	CPML
PMC	PMC	CPML	CPML
PEC	CPML	CPML	CPML
CPML	PEC	CPML	CPML
PMC	CPML	CPML	CPML
CPML	PMC	CPML	CPML
CPML	CPML	CPML	CPML

Table 2 Boundary condition combinations with CPML in three dimensions

$x_{1,min}$	$x_{1,max}$	$x_{2,min}$	$x_{2,max}$	$x_{3,min}$	$x_{3,max}$
Periodic Oblique	Periodic Oblique	Periodic Oblique	Periodic Oblique	CPML	CPML
Periodic	Periodic	Periodic	Periodic	CPML	CPML
Periodic Oblique	Periodic Oblique	CPML	CPML	CPML	CPML
Periodic	Periodic	CPML	CPML	CPML	CPML
CPML	CPML	CPML	CPML	CPML	CPML

References

- [1] P. Harms, R. Mittra, and W. Ko, “Implementation of the Periodic Boundary Condition in the Finite-Difference Time-Domain Algorithm for FSS Structures,” *IEEE Transactions on Antennas and Propagation*, vol. 42, no. 9, pp. 1317–1324, 1994.
- [2] A. Taflove and S. C. Hagness, *Computational Electrodynamics: The Finite-Difference Time-Domain Method*, Boston: Artech House, 3rd ed., 2005.

CHAPTER 4 Building the Correct Mesh

This chapter describes how to build suitable meshes, to control mesh size, and to set up criteria for mesh quality and stability.

Generating Tensor Meshes for EMW

To perform FDTD simulations with EMW, a tensor mesh must be generated using Sentaurus Mesh. The size and quality of the tensor mesh have significant impact on the FDTD simulation time and the accuracy of the results.

NOTE The success of the FDTD simulation depends critically on obtaining a good-quality tensor mesh. An unstable simulation generally indicates the violation of the stability (Courant) criteria, and the first thing to inspect is the size of the smallest mesh cell and the time step.

This chapter reviews some important concepts of tensor-mesh generation for EMW using Sentaurus Mesh (refer to the *Sentaurus™ Mesh User Guide* for details).

Using the Sentaurus Mesh Tensor-Product Generator

The tensor-product meshes for EMW are generated by Sentaurus Mesh using the command:

```
snmesh -t -emw <base_name>_msh
```

Sentaurus Mesh checks the corresponding input files `<base_name>_bnd.tdr` and `<base_name>_msh.cmd`, and then applies the tensor-mesh discretization to a device domain according to the command file specifications. The resulting tensor mesh is saved as `<base_name>_msh.tdr`.

All of the necessary controls to generate the tensor mesh are specified in the `Tensor` section of the command file `<base_name>_msh.cmd`, which can include different `Mesh` and `EMW` subsections:

```
Tensor {  
  Mesh {...}  
  EMW {...}  
}
```

4: Building the Correct Mesh

Using the Sentaurus Mesh Tensor-Product Generator

where:

- The `Mesh` subsection defines the general tensor-grid controls.
- The `EMW` subsection defines dedicated controls for EMW applications.

In the following, the most frequently used controls to obtain a suitable mesh for EMW applications are listed:

```
Mesh {
  maxCellSize = float
  maxCellSize material "materialName" float
  maxCellSize direction "x|y|z" float
  maxCellSize material direction "materialName" "x|y|z" float
  minCellSize = float
  minCellSize direction "x|y|z" float
}
```

where:

- `maxCellSize` specifies the maximum cell size allowed in the tensor grid, directionally or in all spatial directions. For efficient and accurate EMW simulations, it is suggested that `maxCellSize` is smaller than 1/10th of the wave periodicity in the respective materials (that is, more than 10 nodes per wavelength).
- `minCellSize` specifies the minimum cell size in micrometers (default is 0.0001). Since the FDTD time step in EMW depends on the minimum cell size in the tensor grid (the Courant–Friedrichs–Lewy (CFL) stability condition). For efficient and fast EMW simulations with large stable time steps, it is suggested that `minCellSize` is set to a value of 0.001 or larger.

Specifying Nodes per Wavelength in Meshing

Using the `EMW` subsection is an alternative (or additive) solution to control the tensor-mesh generation. The controls in the `EMW` subsection allow for the structure to be meshed by specifying *nodes per wavelength* criteria directly:

```
EMW {
  wavelength = float
  parameter filename = "string"

  nodesperwavelength | npw {
    material "materialName" float
    material direction "materialName" "x|y|z" float
    region "regionName" float
    region direction "regionName" "x|y|z" float
  }
}
```

```
nodesperwavelengthX | npwx = integer
nodesperwavelengthY | npwy = integer
nodesperwavelengthZ | npwz = integer
nodesperwavelength  | npw  = integer

ComplexRefractiveIndex WavelengthDep Real Imag
ComplexRefractiveIndex region "regionName" WavelengthDep [Real | Imag]
ComplexRefractiveIndex material "materialName" WavelengthDep [Real | Imag]

grading off
}
```

where:

- `wavelength` specifies the wavelength of the incident wave in micrometers (default is 0.555).
- `parameter filename` indicates a user-defined parameter file that contains the `ComplexRefractiveIndex` optical database table of the materials that are present in the device structure. Refer to the *Sentaurus™ Device User Guide* for details.
- `nodesperwavelength | npw` defines the value of the nodes per wavelength regionwise or materialwise, directionally or in all spatial directions. Alternatively, the value in each spatial direction can be set for all materials using either of the `npw` statements.
- `ComplexRefractiveIndex` defines the quantity of the complex refractive index evaluated at `wavelength` that should be used to refine according to `nodesperwavelength | npw`.
- The `grading off` statement is used to specify that no mesh grading should be applied at interfaces. Mesh grading causes overly thin layers at interfaces, and the cell size increases with distance from the interface.

NOTE The `grading on` statement (the default) results in a graded mesh that can negatively impact accuracy of the EMW simulation results, which is caused by numeric dispersion.

All controls available for `material` are also available for `region`. A complete list of controls is available in the *Sentaurus™ Mesh User Guide*.

Meshing Examples

Two examples of generating suitable tensor grids for EMW simulations are presented here. First, tensor-grid generation for a simple planar two-layer silicon–air example is performed. Such simple examples are usually used to benchmark FDTD results for `OpticalGeneration` and `PowerFluxDensity` against their analytic values. Second, a Sentaurus Mesh command file is shown for tensor-grid generation that is typical for image sensor applications.

Example 1: Planar Two-Layer Silicon–Air

Tensor-mesh generation with Sentaurus Mesh requires two input files: a boundary file and a command file. The boundary file for a simple planar two-layer silicon–air structure can be generated by Sentaurus Structure Editor using the following script (`simple_dvs.cmd`):

```
(sde:clear)
(sdegeo:create-cuboid (position 0 0 -2.0) (position 0.1 0.1 0.0)
 "Silicon" "R.Substrate")
(sdegeo:create-cuboid (position 0 0 0.0) (position 0.1 0.1 1.0)
 "Ambient" "R.Ambient")
(sdeio:save-tdr-bnd (get-body-list) "simple_bnd.tdr")
```

Running Sentaurus Structure Editor in batch mode using the script (`simple_dvs.cmd`):

```
sde -e -l simple_dvs.cmd
```

produces the boundary file `simple_bnd.tdr`. A possible Sentaurus Mesh command file (`simple_msh.cmd`) for tensor-mesh generation can look like:

```
Tensor {
  Mesh {
    maxCellSize = 0.02
    maxCellSize direction "z" 0.01
    minCellSize = 0.005
  }
}
```

Here, the controls define the maximum cell size allowed in the tensor grid to be $0.02 \mu\text{m}$. It is typical to define a fine mesh in the main propagation direction. The main propagation direction is assumed to be z in this example, so the maximum cell size in the z -direction is limited to $0.01 \mu\text{m}$.

To ensure that the FDTD time step in EMW will be sufficiently large, the minimum cell size allowed is set to $0.005 \mu\text{m}$.

Calling Sentaurus Mesh with:

```
snmesh -t -emw simple_msh
```

produces the tensor-mesh file `simple_msh.tdr`, which is suitable for FDTD simulation. The mesh file can be visualized with Sentaurus Visual using:

```
svisual simple_msh.tdr &
```

Example 2: Image Sensor

In this section, the meshing controls to obtain a suitable tensor mesh for an EMW image sensor simulation are described only, without the Sentaurus Structure Editor command files. For details of generating boundary files with Sentaurus Structure Editor, refer to the *Sentaurus™ Structure Editor User Guide* or the Sentaurus Structure Editor module of the TCAD Sentaurus Tutorial.

Image sensors contain materials with different wavelength-dependent refractive indices and, therefore, different wave periodicities in the materials.

Instead of defining `maxCellSize` for all materials separately to obtain a tensor grid with a reasonable number of nodes per wavelength, the EMW subsection will be used to define the nodes per wavelength criteria directly (`cis_msh.cmd`):

```
Tensor {
  Mesh {
    minCellSize direction "x" 0.005
    minCellSize direction "y" 0.005
    minCellSize direction "z" 0.003
  }
  EMW {
    Parameter Filename = "emw.par"
    Wavelength = 0.6
    ComplexRefractiveIndex WavelengthDep real

    npwx = 10
    npwy = 10
    npwz = 15
    grading off
  }
}
```

In this example, `minCellSize` is specified for each different direction. To fully resolve thin layers in the z-direction, a denser mesh is allowed.

NOTE There is always a trade-off between high geometric resolution (small `minCellSize`) and the FDTD simulation time step in EMW that benefits from a larger `minCellSize`.

In the file `emw.par`, the complex refractive indices are defined, for example:

```
Material = "Silicon" {
  ComplexRefractiveIndex {
    Formula = 1
    NumericalTable (
      ** use NumericalTable
      ** wavelength [um], n [1], k [1]
```

4: Building the Correct Mesh

Meshing Examples

```

...
0.5904  3.969  0.03;
0.5961  3.956  0.027;
0.6019  3.943  0.025;
0.6078  3.931  0.025;
0.6138  3.918  0.024;
...
)
}
}

```

The wavelength is set to $0.6 \mu\text{m}$. The wave periodicity in the material is calculated using the real part of the complex refractive index at wavelength. In addition, `npwx=10` and `npwy=10` define that the tensor grid should consist of at least 10 nodes per wavelength for all materials in the x- and y-direction. In the main propagation direction (z-direction), a finer discretization is chosen with `npwz=15`.

To minimize the impact of numeric dispersion, no mesh grading is used (`grading off`). Applying the command file `cis_msh.cmd` to a typical image sensor boundary will result in a suitable tensor mesh for EMW simulations (see [Figure 3](#)).




Figure 3 (Left) Visualization of a typical image sensor boundary (oxide and vacuum regions are not shown). (Right) Visualization of the corresponding tensor grid generated by Sentaurus Mesh using the command file `cis_msh.cmd`. Grid lines are shown only in silicon. The shape of the lens is given as a staircase caused by the tensor-grid approximation.

Inspecting and Troubleshooting Tensor-Grid Generation

If EMW simulations do not work as expected, the tensor grid is most often the problem. If the grid is too coarse, simulation results are not accurate. If the grid is too fine, the number of cells in the tensor grid will be huge (for example, 200 million cells), which will result in excessive EMW simulation times. If the smallest cell in the tensor grid is too small, the resulting FDTD time step will be small, which will also lead to excessive simulation times.

Therefore, it is recommended to perform some basic EMW inspections:

- Check whether the FDTD time step is in a reasonable range: It should be between 5×10^{-19} s and 5×10^{-17} s for visible light excitations. Note that the FDTD time step is proportional to the minimum cell size.
- Check whether the geometry is approximated well enough by the staircase tensor grid.
- Vary `maxCellSize` or `npw` to analyze whether the EMW simulation results are accurate and independent of meshing parameters.

4: Building the Correct Mesh

Inspecting and Troubleshooting Tensor-Grid Generation

CHAPTER 5 Specifying Material Parameters

This chapter explains how to specify material parameters and dispersive material models for Sentaurus Device Electromagnetic Wave Solver (EMW) simulations.

Introduction

The material parameters used in EMW are based on the complex refractive index (CRI) module. Parameters used in the fundamental equations of the FDTD method (see [Chapter 2 on page 7](#)), such as permittivity and conductivity or dispersive model parameters, are derived from it internally. To maintain backward compatibility, it is still possible to specify these parameters explicitly in the parameter file.

EMW supports the same parameter file specification of the CRI that is used by different tools such as Sentaurus Device and Sentaurus Mesh and, therefore, ensures consistent input data. This includes the C++ application programming interface (API), which allows for the specification of user-defined models.

In general, the CRI is defined by selecting a model in the command file and by specifying the corresponding model parameters for each region or material in the parameter file. A model can be assigned to a material, a region, or the entire device. The name of the parameter file must be given in the `Globals` section using the keyword `ParameterFile`; otherwise, default parameters are used if they exist for a requested material.

Complex Refractive Index Model

To activate the CRI model, a `ComplexRefractiveIndex` section must be defined in the command file that specifies the dependencies of the CRI for a given region or material. If neither a region nor a material is assigned to the `ComplexRefractiveIndex` section, it is assumed that the dependencies apply to all regions of the device structure. EMW supports all dependencies of the CRI given in [Sentaurus™ Device User Guide, Complex Refractive Index Model on page 578](#). However, some dependencies are based on spatially varying fields such as charge carrier density or temperature, which are not natively available in the input tensor-grid file. In this case, an extra TDR file containing the datasets required by the specified dependencies must be provided, which is described in [Spatially Dependent Complex Refractive Index Model on page 35](#).

5: Specifying Material Parameters

Complex Refractive Index Model Interface

For a spatially constant CRI, that is, its value is constant within a region or material, supported dependencies are wavelength and temperature.

The following example shows how to use a CRI in a region called `substrate` whose real and imaginary parts depend on the excitation wavelength and its real part depends on the global device temperature:

```
Globals {
    Temperature = 380    # global device temperature [K]
}

ComplexRefractiveIndex {
    Region = "substrate"
    WavelengthDep = {Real, Imag}
    TemperatureDep = {Real}
}
```

NOTE Region sections always overwrite material sections if, for a given region, both a material and a region section exist in the command file.

NOTE Temperature dependency is supported for both a spatially constant CRI and a spatially dependent CRI. For the former, a global device temperature must be specified in the `Globals` section; for the latter, an external temperature profile must be loaded.

The parameter `Formula` in the corresponding `ComplexRefractiveIndex` section in the parameter file determines the type of wavelength dependency, for example, tabulated values or an analytic formula.

For more details, see [Sentaurus™ Device User Guide, Wavelength Dependency on page 579](#) and [Sentaurus™ Device User Guide, Using Complex Refractive Index on page 581](#).

Complex Refractive Index Model Interface

The complex refractive index model interface (CRIMI) allows the addition of new CRI models. These models must be implemented as C++ functions, and EMW loads the functions at runtime using the dynamic loader. No access to the EMW source code is necessary.

The generated shared object file containing the model implementation can be used together with Sentaurus Device and Sentaurus Mesh.

See [Sentaurus™ Device User Guide, Complex Refractive Index Model Interface on page 586](#) and [Sentaurus™ Mesh User Guide, EMW Subsection for Computing Cell Size Automatically on page 48](#).

Three main steps are required for integrating user-defined models:

- First, a C++ class implementing the CRI model must be written.
- Second, a shared object must be created that can be loaded at runtime.
- Third, the model must be activated in the command file.

The first two steps are explained in detail in the [Sentaurus™ Device User Guide, C++ Application Programming Interface \(API\) on page 586](#), and [Sentaurus™ Device User Guide, Shared Object Code on page 592](#).

To load CRI models into EMW, the `CRIMIPath` search path must be defined in the `Globals` section of the command file. The value of `CRIMIPath` is allowed to contain multiple directory paths, separated by whitespace, for example:

```
Globals {  
    CRIMIPath = ". /home/joe/lib /home/mary/sdevice/lib"  
}
```

For each CRI model that appears in the `ComplexRefractiveIndex` section, the given directories are searched for a corresponding shared object file, for example, `modelname.so.linux64`.

A CRI model can be activated in the `ComplexRefractiveIndex` section of the command file by specifying the name of the model as shown in the following example:

```
ComplexRefractiveIndex {  
    Material = "Silicon"  
    CRIModel = "modelname"  
}
```

NOTE A CRI model name can only contain alphanumeric characters and underscores (`_`). The first character must be either a letter or an underscore. All CRI models can be specified regionwise or materialwise.

Spatially Dependent Complex Refractive Index Model

EMW allows for the definition of a spatially dependent CRI in contrast to a regionwise constant profile. For certain devices, the dependency of the CRI on temperature, carrier concentration, electric field, mole fraction, or any other spatially varying field may have a significant impact on their device characteristics. The CRIMI described in the previous section, paired with the ability to load arbitrary spatially varying field quantities into EMW, provides maximum flexibility for modeling any given CRI profile.

5: Specifying Material Parameters

Spatially Dependent Complex Refractive Index Model

A spatially varying CRI can be either imported directly or defined in terms of the quantities on which it depends, which is controlled by the specified `Type` (`FromFile` or `Inhomogeneous`) in the `ComplexRefractiveIndex` section of the command file. The file from which the CRI or its dependencies are read is specified in the `Globals` section using the `FieldDataFile` keyword.

To model a CRI that depends on wavelength, temperature, and carrier concentration, use the following syntax:

```
Globals {
    FieldDataFile = "external_data_fields.tdr"
}

ComplexRefractiveIndex {
    Type = Inhomogeneous
    WavelengthDep = {Real, Imag}
    CarrierDep = {Real, Imag}
    TemperatureDep = {Real}
}
```

If `Type=FromFile` in the `ComplexRefractiveIndex` section, the TDR file specified by `FieldDataFile` must contain the datasets `cplxRefIndex` and `cplxExtCoeff`, which are associated with the real and imaginary parts of the CRI, respectively.

The datasets in the TDR file may be defined on any arbitrary tensor or mixed-element grid with different region or material names than the EMW input tensor mesh. However, the grids must overlap within the global coordinate system. The CRI will be computed on the grid of the `FieldDataFile` and then linearly interpolated onto the EMW tensor grid.

NOTE If the CRIMI is used (see [Complex Refractive Index Model Interface on page 34](#)), you must specify `Type=Inhomogeneous` in the `ComplexRefractiveIndex` section. By default, all datasets available in the `FieldDataFile` are loaded and can be accessed to compute the CRI. However, they must be registered in the constructor of the respective CRI model before they can be used.

Limitations

The use of a spatially dependent CRI is subject to the following limitations:

- Dispersive media are not supported.
- DFT simulations are not supported.

- Mole fraction dependency is only supported for wavelength dependency using numerical tables and for the CRIMI.
- If `Type=FromFile` in the `ComplexRefractiveIndex` section, the `cplxRefIndex` dataset in the `FieldDataFile` must be defined on the entire domain given by the keywords `Region` and `Material`. Partial overlap will lead to an error stating that zero relative permittivity has been encountered.

Depending on the number of datasets in `FieldDataFile` that will be loaded and interpolated onto the input tensor mesh, the memory usage will increase temporarily during the material initialization phase. However, the memory footprint during the time-stepping loop will not be affected significantly.

Dispersive Model Parameters

To use one of the dispersive models described in [Modeling of Dispersive Media on page 12](#), it is necessary to choose the regions or materials in which the selected model should be applied in the EMW command file. The corresponding dispersive model parameters either are derived from the CRI or must be supplied directly by the user.

Dispersive Model Command Syntax

Activation of the dispersive material requires a separate `DispersiveMedia` section as shown here.

Assuming that materials named `DispMatA` and `DispMatB` in the tensor-product grid are of the dispersive type `Debye`, the following section must be included in the EMW command file:

```
DispersiveMedia {  
  Material = {"DispMatA" "DispMatB" ...}  
  # Region = {"reg1" "reg2" ...}  
  # ExcludeMaterial = {"mat1" "mat2" ...}  
  # ExcludeRegion = {"reg3" "reg4" ...}  
  Model = Debye # or Lorentz or Drude or DrudeLorentz  
  ModelParameters = UserDefined  
  DeltaK = <float>  
  InterfaceAveraging = <identifier>  
}
```

The valid dispersive models are `Debye`, `Drude`, `DrudeLorentz`, `DrudeModLorentz`, `Lorentz`, `ModLorentz`, and `SingleDipoleDrude`. The setting of `DeltaK` (Δk) activates the dispersive model when $k + \Delta k \geq n$. The dispersive model is always activated by setting

5: Specifying Material Parameters

Dispersive Model Parameters

DeltaK to a large number. In addition to setting the dispersive materials by `Material`, you can set the materials by `Region`, `ExcludeMaterial`, and `ExcludeRegion`.

If `InterfaceAveraging=Yes`, a weighted average of the dielectric function in the frequency domain is used at the interface (electric field edges among adjacent cells). If `InterfaceAveraging=No`, EMW uses the material parameter of the material with the highest precedence at the interface (electric field edges among adjacent cells). The criteria for material precedence are:

- Lossy dielectric < Debye < Lorentz < modified Lorentz < Drude < Drude–Lorentz < Drude–modified Lorentz < PMC < PEC.
- Within the same dispersive model, the following parameters (see [Specifying User-Defined Dispersive Model Poles in Parameter File on page 39](#)) are compared in sequence:

`epsilon_static`, `eps_infinity`, `sigma`, `nPole_E`, `E_pole_amplitude`,
`E_relaxation_time`, `E_pole_frequency`, `E_damping_factors`

The material with the highest value has highest precedence.

One limitation of the `InterfaceAveraging` keyword is that it must be `Yes` or `No` for all `DispersiveMedia` sections. Another limitation is that when `InterfaceAveraging=Yes`, all `DispersiveMedia` sections must not use `Model=Debye`. Averaging of the frequency-dependent dielectric function is performed only at interfaces with at least one dispersive region. At interfaces formed by nondispersive regions, only the dielectric constants, that is, ϵ_r , μ_r , ρ , and σ , are averaged.

Additional restrictions can be applied by limiting the dispersive type only to materials defined in `Material` but not in `ExcludeMaterial`, or in regions defined in `Region` but not in `ExcludeRegion`.

NOTE Only one dispersive model can be defined in each `DispersiveMedia` section.

For monochromatic excitations, a promising approach is to use a single-dipole Drude model (see [Unmagnetized Plasma on page 15](#)).

Setting ϵ_∞ to one, the Drude pole frequency (ω_p) and the Drude damping factor (γ_p) can be derived from the CRI. Therefore, the dispersive model `SingleDipoleDrude` must be used in conjunction with the CRI library (see [Complex Refractive Index Model on page 33](#)).

The following `DispersiveMedia` section shows how to use the `SingleDipoleDrude` model:

```
DispersiveMedia {
  Material = {"Gold"}
  Model = SingleDipoleDrude
  ModelParameters = ComputeFromComplexRefractiveIndex
```



```
DeltaK = <float>
}
```

If `ModelParameters` is set to `ComputeFromComplexRefractiveIndex`, the poles of the specific dispersive model are extracted automatically from the CRI values. If `UserDefined` is set, the poles of the dispersive model are loaded from the user-defined poles table of the material parameter file (see [Specifying User-Defined Dispersive Model Poles in Parameter File on page 39](#)).

NOTE `ComputeFromComplexRefractiveIndex` is supported only for the dispersive model `SingleDipoleDrude`.

For a summary of keywords supported in the `DispersiveMedia` section, see [Appendix A on page 99](#). You can consider using the dispersive model in the following situations:

- When $k \geq n$ for a material.
- When the dispersiveness (frequency dependency of n and k) of a material must be captured, for example, in a broadband DFT simulation.

Specifying User-Defined Dispersive Model Poles in Parameter File

The following syntax sets a material with the types Debye, Lorentz, modified Lorentz, and Drude, respectively, in a material parameter file:

```
Material = "Debye_materialname" {
  EMW {
    mu_r = mu_r
    sigma_m = sigma_m
    DebyeModel (
      Epsilon_static = epsilon_s
      Epsilon_inf = epsilon_infty
      Number_E_poles = N_p
      E_polesTable (
        # amplitude, relaxation times
        A_1 tau_1
        A_2 tau_2
        ...
      )
    )
  }
}

Material = "Lorentz_materialname" {
  EMW {
    mu_r = mu_r
```

5: Specifying Material Parameters

Dispersive Model Parameters

```
sigma_m = sigma_m
LorentzModel (
  Epsilon_static = epsilon_s
  Epsilon_inf = epsilon_infty
  Number_E_poles = N_p
  E_polesTable (
    # amplitude, frequency (Hz), damping factor (rad/s)
    A_1 f_1 gamma_1
    A_2 f_2 gamma_2
    ...
  )
)
}

Material = "Modified_Lorentz_materialname" {
  EMW {
    mu_r = mu_r
    sigma_m = sigma_m
    ModLorentzModel (
      Epsilon_static = epsilon_s
      Epsilon_inf = epsilon_infty
      Number_E_poles = N_p
      E_polesTable (
        # amplitude, frequency (Hz), damping factor (rad/s),
        # damping factor prime (rad/s)
        A_1 f_1 gamma_1 gamma_prime_1
        A_2 f_2 gamma_2 gamma_prime_2
        ...
      )
    )
  }
}

Material = "Drude_materialname" {
  EMW {
    mu_r = mu_r
    sigma_m = sigma_m
    DrudeModel (
      Epsilon_inf = epsilon_infty
      Number_E_poles = N_p
      E_polesTable (
        # frequency (Hz) and damping factor (rad/s)
        f_1 gamma_1
        f_2 gamma_2
        ...
      )
    )
  }
}
```

For the Drude–Lorentz model, both the `LorentzModel` and `DrudeModel` sections must be specified simultaneously:

```
Material = "DrudeLorentz_materialname" {
  EMW {
    mu_r = mu_r
    sigma_m = sigma_m
    # Both Lorentz and Drude models are specified
    # to give a combination Drude-Lorentz model
    LorentzModel (
      Epsilon_static = epsilon_s
      Epsilon_inf = epsilon_infty
      Number_E_poles = N_p
      E_polesTable (
        # amplitude, frequency (Hz), damping factor (rad/s)
        A_1 f_1 gamma_1
        A_2 f_2 gamma_2
        ...
      )
    )
    DrudeModel (
      Epsilon_inf = epsilon_infty
      Number_E_poles = N_p
      E_polesTable (
        # frequency (Hz) and damping factor (rad/s)
        f_1 gamma_1
        f_2 gamma_2
        ...
      )
    )
  }
}
```

For the Drude–modified Lorentz model, both the `ModLorentzModel` and `DrudeModel` sections must be specified simultaneously:

```
Material = "DrudeModifiedLorentz_materialname" {
  EMW {
    mu_r = mu_r
    sigma_m = sigma_m
    # Both ModLorentz and Drude models are specified to give
    # a combination Drude-modified Lorentz model
    ModLorentzModel (
      Epsilon_static = epsilon_s
      Epsilon_inf = epsilon_infty
      Number_E_poles = N_p
      E_polesTable (
        # amplitude, frequency (Hz), damping factor (rad/s),
        # damping factor prime (rad/s)

```

5: Specifying Material Parameters

Explicit Specification of EMW Material Parameters

```
        A_1 f_1 gamma_1 gamma_prime_1
        A_2 f_2 gamma_2 gamma_prime_2
    )
)
DrudeModel (
    Epsilon_inf = epsilon_infty
    Number_E_poles = N_p
    E_polesTable (
        # frequency (Hz) and damping factor (rad/s)
        f_1 gamma_1
        f_2 gamma_2
        ...
    )
)
}
}
```

Explicit Specification of EMW Material Parameters

If no `ComplexRefractiveIndex` section in the command file exists for a specific region or material, EMW assumes that its material parameters are specified explicitly. To this end, an EMW section must be defined in the material parameter file where permittivity, permeability, and conductivity values are listed. For most simulations, the specification of values for the permittivity and conductivity is sufficient.

The following examples show EMW sections that should be added to the parameter file if the CRI model is not chosen.

For a materialwise definition, use:

```
Material = "Si3N4" {
    EMW {
        epsilon_r = 2.56
        mu_r      = 1.0
        sigma     = 0.0
        sigma_m   = 0.0
    }
}
```

For a regionwise definition, use:

```
Region = "Substrate" {
    EMW {
        epsilon_r = 16.6818
        mu_r      = 1.0
        sigma     = 10068.5
    }
}
```

```
    sigma_m = 0.0  
  }  
}
```

NOTE Region sections always overwrite material sections if, for a given region, both a material and a region section exist in the parameter file.

NOTE Since magnetic material is not supported, it is required that $\mu_r=1.0$ and $\sigma_m=0.0$ for all materials except PEC and PMC materials.

PEC and PMC Materials

Perfect electric conductor (PEC) and perfect magnetic conductor (PMC) materials are defined as materials with zero tangential components of E- and H-fields, respectively.

The reason for replacing lossy materials by PEC and PMC is to see the ideal situation whereby the electric and magnetic losses of a system are zero.

For a two-layer structure with vacuum (region `vac`) above a gold substrate (region `substrate`), the following are equivalent sections to force the substrate to be of PEC material:

```
PECMedia {  
  Region = {"substrate"}  
}  
  
PECMedia {  
  ExcludeRegion = {"vac"}  
}  
  
PECMedia {  
  Material = {"Gold"}  
}  
  
PECMedia {  
  ExcludeMaterial = {"Vacuum"}  
}
```

In a similar manner, the region or material can be set to PMC by using the `PMCMedia` section.

Precedence of Material Specification

In complex setups, different material models are assigned to specific regions or materials using the keywords `Region`, `Material`, `ExcludeRegion`, and `ExcludeMaterial`, in the respective material model section.

If you specify different material models for the same region, the following precedence applies (highest priority to lowest priority):

1. `PECMedia`
2. `PMCMedia`
3. `DispersiveMedia`
4. `ComplexRefractiveIndex`
5. Explicit specification in `EMW` section of parameter file

This chapter describes how to specify excitations.

Overview

An excitation is defined by its spatial and temporal dependencies. The spatial dependency is characterized by a constant phase wavefront whose propagation direction and polarization can be specified by the user. For the temporal dependency, either a harmonic or a Gaussian signal is applied. Both signals can be ramped up from zero to maximum amplitude over a given number of periods to reduce numeric instabilities.

EMW provides several excitation sources to model scattering problems. The basics are plane wave excitation and a spatial Gaussian beam that can be propagated at an angle from the defined excitation plane. The defined excitation plane arises from the total-field scattered-field (TFSF) formalism, described in [Total-Field Scattered-Field](#).

Additional excitation sources have been implemented to facilitate the modeling of experimental setups, such as that commonly used in the design of CMOS image sensors. These additional sources include an incoherent illumination source as well as an interface to input the complex vectorial beams from the Synopsys CODE V® tool.

Total-Field Scattered-Field

In EMW, all excitations have been implemented using the TFSF formulation. This excitation method is based on splitting the simulation space into a total-field zone and a scattered-field zone. The excitation source has an effect at the interface between the two zones such that the total field \mathbf{E}_T and the scattered field \mathbf{E}_S are related by:

$$\mathbf{E}_T = \mathbf{E}_S + \mathbf{E}_I \quad (22)$$

where \mathbf{E}_I denotes the excitation field (also called the incident field). Detailed descriptions of the TFSF technique can be found in the literature [1].

The TFSF excitation is used mainly for scattering problems, where a target inside the simulation space is impinged by an electromagnetic wave incident from the outside. In this case, the target is enclosed inside a total-field zone and the outer part of the simulation domain is the scattered-field zone.

6: Specifying Excitations

Plane Waves

In general, the geometric information associated with a TFSF excitation consists of a box that must be defined such that the scattering object is completely inside the box, that is, the total-field zone must be a closed volume. If periodic boundaries are present, a plane (in three dimensions) or a line (in two dimensions) is sufficient to separate the two regions. In this case, the total-field zone is extended to infinity in the lateral directions and can still be considered a closed volume.




Figure 4 TFSF boundary (*dashed line*) for (*left*) nonperiodic and (*right*) periodic structures

Plane Waves

Parameters specifying the plane wave excitation such as propagation direction and polarization are defined in the `PlaneWaveExcitation` section of the command file.

Specifying Excitation Regions or Boxes

The TFSF boundary is most conveniently defined by specifying the opposing corners of a box in the `PlaneWaveExcitation` section using the keywords `BoxCorner1` and `BoxCorner2`. If periodic boundary conditions are applied to the sides, the specified box must define a plane in three dimensions or a line in two dimensions.

Alternatively, a special box region representing the excitation plane can be defined when building the tensor-grid file with Sentaurus Mesh (see [Sentaurus™ Mesh User Guide, Box Subsection for Plotting on page 52](#)). This region can be referenced in the `PlaneWaveExcitation` section using the keyword `Region`.

NOTE In both cases, it is recommended not to have material interfaces or simulation domain boundaries within a three-cell layer of a TFSF boundary for numeric reasons.

To specify a truncated plane wave in the $z = 0.05 \mu\text{m}$ plane with a $0.6 \times 0.6 \mu\text{m}^2$ window, you can use:

```
TruncatedPlaneWaveExcitation {
  BoxCorner1 = {0.2, 0.2, 0.05} # um
  BoxCorner2 = {0.8, 0.8, 0.05} # um
  ...
}
```

Due to the truncation, the plane-wave front diverges as it propagates away from the excitation plane. A common use of the truncated plane wave is to excite wave propagation in a waveguide. In this case, the truncated plane-wave excitation plane is placed near and parallel to the open facet of the waveguide. The area of the truncation window is set similar to the cross-sectional area of the open facet of the waveguide.

Specifying Direction and Polarization

Using ζ for the coordinate along the propagation direction, the plane wave is defined as:

$$\mathbf{E}(\mathbf{r}, t) = s(\zeta - vt)\hat{\mathbf{p}} \quad (23)$$

$$\mathbf{H}(\mathbf{r}, t) = \sqrt{\frac{\epsilon}{\mu}}\hat{\mathbf{k}} \times \mathbf{E}(\mathbf{r}, t) \quad (24)$$

where:

- s is the signal.
- v is the phase velocity of the medium.
- $\hat{\mathbf{p}}$ is the unit vector specifying the polarization direction.
- $\hat{\mathbf{k}}$ is the unit wave vector of the plane wave.

In EMW, the propagation direction is defined by the two parameters `Theta` and `Phi`, which denote the angles in degrees from the z -axis and x -axis, respectively.

6: Specifying Excitations

Plane Waves

A third parameter Ψ is used to set the polarization angle, which measures the angle between H and the $z \times \hat{k}$ axis (see Figure 5). In this definition, $\Psi = 90^\circ$ and $\Psi = 270^\circ$ correspond to TE polarization; whereas, $\Psi = 0^\circ$ and $\Psi = 180^\circ$ correspond to TM polarization.




Figure 5 Definition of coordinate system for 3D plane wave excitation and examples of parameters of 3D plane wave

Below is an example for the command file specification of a typical time-harmonic plane-wave excitation in three dimensions:

```
PlaneWaveExcitation {
  Amplitude = 1          # [V/m]
  Wavelength = 500      # [nm]
  Theta = 30
  Phi = 45
  Psi = 0
  Signal = Harmonic
  NRise = 5
  BoxCorner1 = {-1, -1, 3}
  BoxCorner2 = {1, 1, 3}
}
```

Two-dimensional simulations are performed by extruding the 2D structure by one layer in the third dimension (z-direction). For ease of use, an alternate definition scheme exists for this case. If `Polarization=TE` or `Polarization=TM` is set in the respective `PlaneWaveExcitation` section, the plane wave is completely determined when the parameter `Theta` is specified (see [Figure 6](#)).

For the general polarization case, that is, with neither TE nor TM selected, an additional angle `Psi` is defined in the same way as in the full 3D case, with `Psi = 0°` as default. In addition, you can specify a real value in the interval `[0,1]` for `Polarization`, where `Polarization=0` refers to TM excitations, and `Polarization=1` refers to TE excitations.

A simple relationship between `Psi` and `Polarization` can be established:
$$\text{Polarization} = \sin^2(\text{Psi}).$$

NOTE This plane wave representation is valid only for homogeneous and loss-free domains, which means that all field components belonging to the excitation region should have identical material properties.




Figure 6 Definition of angle of incidence of 2D plane wave, where TE and TM follow Taflove and Hagness definition (see note below): (left to right) `Psi=0°`, `90°`, and `45°`

NOTE TE and TM refer to the definition used by Taflove and Hagness [1], that is, TM (transverse magnetic) defines the magnetic field perpendicular to the z-direction.

Specifying Elliptical Polarization

By default, the plane wave excitation is linearly polarized, that is, the E-field and H-field vectors always maintain fixed directions as the incident wave propagates. It is also possible to simulate plane waves that are polarized elliptically by defining the polarization parameters `EllipticalPolarizationMagnitude` and `EllipticalPolarizationPhase` in the `PlaneWaveExcitation` section.

6: Specifying Excitations

Spatially Incoherent Illumination

For simplicity, consider a linearly polarized plane wave traveling in the z-direction, $\vec{E}(t) = E_0 \hat{x} \cos(\omega t - kz)$. With the polarization parameters defined, the plane wave reads as:

$$\vec{E}(t) = E_0 \frac{\hat{x} \cos(\omega t - kz) + \rho \hat{y} \cos\left(\omega t - kz + \frac{\pi}{180} \delta\right)}{\sqrt{1 + \rho^2}} \quad (25)$$

where:

- ω is the angular frequency.
- k is the propagation constant.
- ρ is the ratio of the polarization magnitude of the major and minor axes.
- δ is the phase offset between the major and minor axes.

Therefore, the direction of the E-field can change as the wave propagates in space or as the time varies. When $\rho = 1^\circ$ and $\delta = 90^\circ$, the plane wave is a circularly polarized wave.

An example of specifying a circularly polarized plane wave in the command file is:

```
PlaneWaveExcitation {  
    ...  
    Theta = 180  
    Phi = 0  
    Psi = 0  
    EllipticalPolarizationMagnitude = 1.0  
    EllipticalPolarizationPhase = 90  
}
```

Spatially Incoherent Illumination

To model an incoherent illumination due to a source of finite extent, you must sum the fields contributed by plane waves incident from different directions [3]. Assuming the light passes through a circular pupil and a circular objective lens before reaching the structure on the focal plane, the incident angles are limited by the half-extended angle of the objective:

$$\theta_{\text{obj}} = \text{asin}(\sigma \text{NA}), \text{ for } \sigma \text{NA} < 1 \quad (26)$$

where NA is the numerical aperture of the objective lens. For circular source and pupils, the partial coherence factor σ is defined as the ratio of the source image dimension to the pupil size [4].

Since the incident angles are confined in a cone, you can synthesize the spatially incoherent illumination by a finite number of plane waves with different incident angles. The greater the number of plane waves, the more accurately the incoherent illumination can be represented.

However, each incident angle corresponds to one FDTD simulation. Therefore, you may want to limit the number of plane waves to obtain satisfactory results within a reasonable simulation time.

An example of specifying a spatially incoherent illumination in the command file is:

```
PlaneWaveExcitation {
    ...
    PartialCoherenceFactor = 1.0 # ratio of source image dimension to pupil size
    NumericalAperture = 0.5     # half-extended angle of objective lens = 30 deg
    NumberOfPlaneWaves = 4     # number of plane waves for incoherent excitation
}
```

Gaussian Beam or Gaussian Field Distribution

For applications involving converging or diverging light beams, such as light passing through a lens, it is helpful to use spatially Gaussian-distributed incident fields on the TFSF excitation plane. EMW adopts the formulation in [2] for the implementation of the Gaussian beam (see [Figure 7 on page 53](#)). Electromagnetic fields at the TFSF excitation plane are calculated by the scalar paraxial solution of a 3D fundamental-mode Gaussian beam:

$$E(r, z') = E_{\max} \frac{w_0}{w(z')} \exp\left[\frac{-r^2}{w(z')^2}\right] \exp\left[-ikz' - ik\frac{-r^2}{2R(z')} + i\xi(z')\right] \quad (27)$$

Following the procedure in [2] and solving the scalar wave equation in two dimensions yield the beam profile in two dimensions:

$$E(r, z') = E_{\max} \sqrt{\frac{w_0}{w(z')}} \exp\left[\frac{-r^2}{w(z')^2}\right] \exp\left[-ikz' - ik\frac{-r^2}{2R(z')} + i\frac{\xi(z')}{2}\right] \quad (28)$$

In [Eq. 27](#) and [Eq. 28](#):

- r is the radial distance from the center axis of the beam.
- z' is the axial distance from the beam waist.
- i is the imaginary unit (for which $i^2 = -1$).
- $k = 2\pi/\lambda$ is the wave number.
- w_0 is the radius of the beam waist.
- $z'_R = \pi w_0^2/\lambda$ is the Rayleigh length.
- $w(z') = w_0 \sqrt{1 + (z'/z'_R)^2}$ is the radius at which the field amplitude and the intensity drop to $1/e$ and $1/e^2$ of their axial values, respectively.

6: Specifying Excitations

Gaussian Beam or Gaussian Field Distribution

- $R(z') = z'[1 + (z'_R/z')^2]$ is the radius of curvature of the wave fronts of the beam.
- $\xi(z') = \text{atan}(z'/z'_R)$ is the Gouy phase shift, an extra contribution to the phase that is seen in Gaussian beams.

The peak electric field E_{\max} can be set directly using the keyword `Amplitude` or can be calculated from the `Intensity` (I_{\max}). Alternatively, the total power P_{\max} of the beam can be set by `BeamPower`. In three dimensions, $E_{\max} = 2\sqrt{Z_0 P_{\max} / \pi n / w_0}$. In two dimensions, $E_{\max} = (2\sqrt{2/\pi} Z_0 P_{\max} / n L_z w_0)^{1/2}$. Here, Z_0 and n denote, respectively, the vacuum wave impedance and the refractive index of the medium at the excitation plane. L_z is the dimensionality constant along the third dimension in the 2D case, for which the default value is $1 \mu\text{m}$. The box corners (P_1, P_2 set by `BoxCorner1, BoxCorner2`) define the truncation window of the Gaussian beam. For oblique incidence, when the axial direction of the beam is not perpendicular to the excitation plane, the Gaussian beam is projected onto the excitation plane.

Since the implementation of Gaussian beams is based on a scalar paraxial solution, the beam quality or, from another perspective, the deviation of the beam spatial profile from the Gaussian is determined by how well the paraxial approximation ($w_0 > \lambda$) is satisfied. In general, a smaller beam waist (tighter focus), a focal point farther away from the excitation plane, and a more tilted beam lead to a less accurate Gaussian beam profile. When the excitation condition deviates from that enforced by the paraxial approximation, enlarging the excitation plane or increasing the mesh density only leads to a marginal improvement of the results.

Due to the large phase difference in the wave front at the excitation plane, users must specify a slow ramp-up of the field to a harmonic signal.

NOTE Temporal dependency (`Signal=Gauss`) is disabled for Gaussian beam excitation.

For example, to specify a truncated, oblique, Gaussian beam on the $z = 0.05 \mu\text{m}$ plane (defined by box corners) within a $2 \times 2 \mu\text{m}^2$ window and with a peak intensity of 0.1 W/cm^2 , the following syntax applies:

```
GaussianBeamExcitation {
  BoxCorner1 = {-1, -1, 0.05}
  BoxCorner2 = {1, 1, 0.05}
  BeamCenter = {0.3, 0.0, -0.4}
  BeamRadius = 0.10           # um
  Theta = 135
  Phi = 0
  ...
  Intensity = 0.1             # in W/cm^2
}
```




Figure 7 Schematic of Gaussian beam excitation

Temporal Dependency

Signals are used to define the time dependency of the incident field in the respective excitation section. By default, a ramped harmonic signal of the following form is used:

$$s(t) = \begin{cases} A \left\{ 1 - \exp \left[\frac{-(t-t_0)^2}{\tau^2} \right] \right\} \sin \left(\frac{2\pi c_0}{\lambda} t + \varphi \right) & \text{for } t > t_0 \\ 0 & \text{otherwise} \end{cases} \quad (29)$$

where:

- $\tau = \frac{N_\tau \lambda}{2c_0}$ determines the rise of the signal from zero to its maximum amplitude.
- λ denotes the wavelength.

6: Specifying Excitations

Temporal Dependency

- φ denotes the phase.
- The parameter t_0 specifies a delay for the ramping of the signal.
- N_τ is the number of signal periods before the full amplitude is reached (see [Table 3 on page 54](#) for corresponding keywords).
- c_0 is the vacuum speed of light.

For amplitude A and wavelength λ , the intensity I and the frequency f can be specified alternatively, according to the following conversion formulas:

$$\begin{aligned} A &= \sqrt{2ZI} \\ \lambda &= \frac{c_0}{f} \end{aligned} \quad (30)$$

where Z is the impedance of the excitation medium.

Specifying `Gauss` as an argument of the keyword `Signal` selects a Gaussian signal modulated by a sinusoidal wave as time excitation of the form:

$$s(t) = A \exp\left[\frac{-(t-t_0)^2}{2\sigma^2}\right] \sin\left(\frac{2\pi c_0}{\lambda}t + \varphi\right) \quad (31)$$

The width of the Gaussian envelope is controlled by $\sigma = \frac{N_\sigma \lambda}{c_0}$. For all other keywords, see [Table 3](#).

Table 3 Main keywords to control temporal signals

Symbol	Keyword	Unit
A	Amplitude	V/m
N_τ	Nrise	Number of periods
N_σ	Sigma	Number of periods
λ	Wavelength	Nm
φ	Phase	degree
t_0	Delay	Number of periods
f	Frequency	Hz
I	Intensity	W/cm ²

Figure 8 illustrates the harmonic and Gaussian signal shapes.




Figure 8 Examples of (*left*) harmonic signal and (*right*) Gaussian signal for $A = 1$, $\lambda = 0.6 \mu\text{m}$, $N_\sigma = N_\tau = 4$

CODE V Interface

EMW uses the `CodeVExcitation` section to specify the excitation type that inputs complex vectorial field data from CODE V. The equivalence theorem is used to set up such an excitation on the excitation plane using the TFSF formalism.

CODE V is a tool that is used to design and optimize a complex lens assembly. The interface between CODE V and EMW provides a seamless flow of optical simulation and design of CMOS image sensor devices.

The syntax to specify CODE V beam excitation is:

```
CodeVExcitation {
  InputDataFile = {"zf.dat", "zfPlus20.dat"}
  AnchorPoint1 = {-1, -1, 0.28}           # [um]
  AnchorPoint2 = {-1, -1, 0.30}           # [um]
  Wavelength = 300                         # [nm]
  Signal = Harmonic
  NRise = 20
  Delay = 0
  AmplitudeScaling = 1
  PhaseShift = 0
}
```

where:

- `InputDataFile` specifies two slices of complex electric-field data that are output from CODE V. The beam is assumed to propagate from the first slice to the second slice.
- `AnchorPoint1` and `AnchorPoint2` specify the physical coordinates to position the two slices of data in EMW.

6: Specifying Excitations

CODE V Interface

- As the absolute amplitude and the phase of the complex electric field are provided in the data files, `AmplitudeScaling` and `PhaseShift` are used to specify a relative amplitude scaling and phase shift.

For a summary of keywords supported in the `CodeVExcitation` section, see [Appendix A on page 99](#).

Typically, the content of the `zf.dat` file is as follows:

```
Wavelength:      300      nm
Grid spacing:    0.000020      0.000020      mm
Array size:      101      101
...
<field data>
...
```

[Table 4](#) describes the keywords in the `zf.dat` file.

Table 4 Keywords in CODE V data file

Keyword	Description	Unit
Wavelength	Wavelength of the excitation.	nm
Grid spacing	Grid spacing in the x- and y-directions.	mm
Array size	Number of electric field values in the x- and y-directions.	1

The field data part has the following format:

```
ExRe (x1, y1)  ExIm (x1, y1)  EyRe (x1, y1)  EyIm (x1, y1)  EzRe (x1, y1)
EzIm (x1, y1)  ExRe (x2, y1)  ExIm (x2, y1)  EyRe (x2, y1)  EyIm (x2, y1)
EzRe (x2, y1)  EzIm (x2, y1)  ...            ExRe (xn, y1)  ExIm (xn, y1)
EyRe (xn, y1)  EyIm (xn, y1)  EzRe (xn, y1)  EzIm (xn, y1)
...
ExRe (x1, yn)  ExIm (x1, yn)  EyRe (x1, yn)  EyIm (x1, yn)  EzRe (x1, yn)
EzIm (x1, yn)  ExRe (x2, yn)  ExIm (x2, yn)  EyRe (x2, yn)  EyIm (x2, yn)
EzRe (x2, yn)  EzIm (x2, yn)  ...            ExRe (xn, yn)  ExIm (xn, yn)
EyRe (xn, yn)  EyIm (xn, yn)  EzRe (xn, yn)  EzIm (xn, yn)
```

The order of the x- and y-indices is:

```
x1 < x2 < ... < xn
y1 > y2 > ... > yn
```

where $(x1, yn)$ correspond to the indices of the anchor point of the field data.

The limitations of CODE V beam excitation are:

- Beams in two dimensions are not supported.
- The beam propagation direction must be in the z-direction. The two slices of data must be taken in the xy plane.
- The two slices of data must be taken in vacuum or air ($\epsilon_r = 1$).
- To obtain the correct beam propagation, the two slices of data must vanish before reaching the xy boundaries. If this is not satisfied, spurious diffraction will emerge.
- The x (y) coordinates of AnchorPoint1 and AnchorPoint2 must be the same. Their z-coordinate difference must be the same as the EMW z-cell size between slices corresponding to AnchorPoint1 and AnchorPoint2.
- Only harmonic signal is allowed in the CodeVExcitation section.
- The CodeVExcitation section can be used only with the boundary conditions in Table 5.

Table 5 Allowed boundary conditions for CodeVExcitation section

x_{\min}	x_{\max}	y_{\min}	y_{\max}	z_{\min}	z_{\max}
CPML	CPML	CPML	CPML	CPML	CPML
Periodic	Periodic	Periodic	Periodic	CPML	CPML

References

- [1] A. Taflove and S. C. Hagness, *Computational Electrodynamics: The Finite-Difference Time-Domain Method*, Boston: Artech House, 3rd ed., 2005.
- [2] H. Kogelnik and T. Li, "Laser Beams and Resonators," *Applied Optics*, vol. 5, no. 10, pp. 1550–1567, 1966.
- [3] J. W. Goodman, *Introduction to Fourier Optics*, Englewood, Colorado: Roberts & Company, 3rd ed., 2005.
- [4] A. K.-K. Wong, *Optical Imaging in Projection Microlithography*, Tutorial Texts in Optical Engineering, vol. TT66, Bellingham, Washington: SPIE Press, 2005.

6: Specifying Excitations

References

This chapter discusses issues pertaining to terminating simulations.

Options for Terminating FDTD Time-Stepping Loop

There are different options for terminating the FDTD time-stepping loop:

- Setting the total simulation time directly.

This option is controlled by the keyword `TotalSimulationTime` or `TotalTimeSteps` in the `Globals` section, which allows you to determine the simulation time either directly or in terms of the total number of time steps, respectively. However, the final state of the simulation is unclear.

- Using detectors to define the termination criteria.

Applying a detector allows you to terminate the computation as soon as a certain state (such as steady state) or situation is reached. This is especially important when quantities are computed that require the instantaneous electromagnetic field distribution to be time harmonic within part or all of the simulation domain (see [Extractors on page 68](#) and [Sensors on page 70](#)).

- Sending the POSIX interrupt signal `INT`.

Sending the POSIX interrupt signal `INT` to the running process terminates the simulation. However, before quitting the process, any pending plots, monitors, extractors, or sensors scheduled for the regular completion of the simulation will be performed unless a second signal `INT` is received by the process. In that case, the simulation terminates immediately. A signal can be sent to a process by invoking the `kill` command, for example:

```
kill -s INT <pid>
```

where `<pid>` is the process ID, which can be extracted from the `.log` file. In an interactive shell, use the shortcut key combination `Ctrl+C` to send the signal `INT` to the active process.

These options for terminating a simulation are nonexclusive. For example, the first option can be used to limit the total simulation time for a simulation that shows poor or no convergence with respect to the termination criterion defined by the detector. Without such a limit, a simulation could progress indefinitely.

Detectors

A detector works on a specified domain, which may be defined by a region of the tensor mesh or by specifying a box using the keywords `BoxCorner1` and `BoxCorner2` (see [Chapter 8 on page 63](#)). If nothing is specified, the detector is applied to the entire simulation domain.

For the most common case of `periodicoblique` boundary conditions, the detector tracks the total energy in the system at each detection period. In all other cases, a more stringent criterion is used, which checks the value of each electric field component at each detection period. However, this latter criterion tends to show noisy behavior especially for structures with high internal scattering.

By default, the period is derived from the wavelength of the excitation signal. You can explicitly select the period using the keyword `Frequency`. In both cases, the simulation time step is adjusted (reduced) automatically to an integer fraction of the excitation signal period.

By default, the termination criterion considers all grid nodes within the detector domain. When using the tracking criterion for electric field components, you can further reduce the number of evaluations for the corresponding coordinate direction by providing a skip factor using the keywords `StepX`, `StepY`, and `StepZ`. For example, choosing a skip factor of 20 instead of 10 (default) for each coordinate direction reduces the computation complexity of the detector by approximately a factor of eight.

The termination criterion depends on the time-domain excitation signal in the `Excitation` section and the type of the detector. Different cases are shown in [Table 6](#).

Table 6 Detector termination criterion for different time-domain signal and detector types

Signal	Type	Convergence criterion
Harmonic	Periodic	For simulations using <code>periodicoblique</code> boundary conditions, the total energy in the system is tracked, and its relative change is compared to the value specified by the keyword <code>Tolerance</code> . For all other simulations, each electrical field component is compared to the last detection period. The difference divided by the maximum field value in the simulation domain must be less than the value specified by <code>Tolerance</code> .
Harmonic	Decayed	Not allowed.
Gauss	Periodic	For each electrical field component, its maximum field value at the current detection period divided by its maximum field value, at all previous detection periods, is less than the value specified by the keyword <code>Tolerance</code> .
Gauss	Decayed	For each electrical field component, its maximum field value at the current detection period divided by the amplitude of the excitation Gaussian time pulse is less than the value specified by the keyword <code>Tolerance</code> .

NOTE Detectors can slow down a simulation considerably. This is especially critical if a large detector domain with small step parameters is used, for example, the entire simulation domain for a large tensor mesh in terms of the number of grid cells.

A detector also can terminate simulations that diverge or run into numeric problems due to, for example, a mesh that is too coarse leading to nonfinite field (NaN) values. If the keyword `BreakOnError` is set to `Yes`, the simulation stops immediately; however, the final `Plot` or `Extractor` sections are still processed. The exit code of such simulations is set to a nonzero value so that a corresponding node in Sentaurus Workbench is flagged as failed. Similarly, the keyword `FailureOnUnreachedTolerance` controls the exit code of a simulation that has not fallen below the value of `Tolerance` specified in the command file.

The keywords `StartTime` and `StartTick` allow you to restrict the time interval during which the detector is actually applied. Since the evaluation of the termination criterion for all field components may slow down the simulation substantially, it can be beneficial to delay the application of the detector. Therefore, `StartTick` is offset to a reasonable value automatically, according to the excitation signal and the `Tolerance`. To overwrite the automatic value, specify `StartTick` explicitly.

NOTE If the MPI parallelization is activated, the detector must be applied to the entire simulation domain to prevent slowing down the MPI speedup.

In the course of the simulation, the `Detector` section writes the maximum deviation of the entire `Detector` domain and its location therein to standard output and the log file. How the maximum deviation is computed depends on the excitation signal and the detector type, which is described in [Table 6 on page 60](#). Sometimes, it can be useful to monitor the convergence behavior visually to have a better impression of the current state of the simulation and to decide whether an increased number of time steps would significantly reduce the maximum deviation and, therefore, lead to more accurate results.

For this purpose, the maximum deviation can be plotted over time or over the number of time steps (denoted as `TickStep`). The data is saved continuously in the `ResultFile` specified in the `Globals` section of the command file and can be plotted in Sentaurus Visual. Clicking the **Reload** button in Sentaurus Visual during the simulation adds any new data points computed in the intervening time to the existing curve.

For simulations where each electric field component is compared to the last detection period, the location of the maximum deviation is plotted as well. It might not be unique because it is possible that several vertices exhibit the same deviation. In parallelized simulations (shared-memory parallelization (SMP) and distributed processing (DP)), the reported location of the maximum deviation can vary for different runs of the same simulation.

NOTE In DP simulations, the maximum location reported may lie outside the physical device structure in one of the CPML regions.

7: Terminating Simulations

Detectors

CHAPTER 8 Extracting and Visualizing Results

This chapter presents how to extract useful quantities from EMW simulation results.

Overview

EMW offers several ways of extracting and visualizing its simulation results. Besides plotting spatially resolved data such as electrical field values and material parameters that were used in the FDTD formulation, integrated data derived from it can be generated. Material parameters such as the complex refractive index can be output using plots. Field values such as the electric field can be accessed using plots or monitors. Derived physical quantities such as the absorbed photon density are computed by extractors or sensors. While extractors calculate derived physical quantities in a given geometric domain, the output of sensors is usually the result of integrating a specific quantity over a user-defined surface or volume. Whether the integration domain is a surface or a volume depends on the quantity of interest.

A major difference between plots, monitors, and sensors on the one hand and extractors on the other hand is that the former can generate output at any time step during the simulation, while the latter is restricted to the end of the simulation. If a detector has been specified and the given tolerance has not been reached before the application of extractors or sensors, a warning message is issued. Certain quantities computed by extractors and sensors rely on a quasistationary solution of the FDTD equations to produce physically meaningful results.

A common feature of plots, extractors, and sensors is the selection of an applicable 2D or 3D domain by specifying one of the following options:

- One or more regions of the corresponding grid
- One or more materials of the corresponding grid (applies only to sensors)
- A box with the coordinates of two opposing corners using the keywords `BoxCorner1` and `BoxCorner2`
- A plane (a line in two dimensions) normal to one of the coordinate axes using the keywords `PlaneX`, `PlaneY`, and `PlaneZ`

NOTE Only sensors support the specification of multiple domains (see [Using Multiple Domains in a Sensor on page 72](#) for details). However, regions and materials as well as a box and a plane are mutually exclusive.

8: Extracting and Visualizing Results

Plots

Monitors are used to probe field values at specific points in the grid defined by their coordinates. For plots and extractors, data can be output to either a tensor grid or a mixed-element grid. On the other hand, the results of monitors and sensors are written to a .plt file, similar to the current plot file in Sentaurus Device (see [Sentaurus™ Device User Guide, Current File on page 107](#)). The quantities of interest are specified using the keyword `Quantity`.

NOTE The data format of the grid file specified in the `Globals` section determines the data format to be used for plots and extractors.

NOTE You can control further compression, beyond a basic standard compression for plot, sensor, extractor, and save files as well as the result file, by specifying `CompressTDR=Yes | No` in the `Globals` section.

Extractors and sensors can be used in either of two ways:

- They are applied during (sensors only) or at the end of the simulation after the FDTD time-stepping loop.
- They are applied to previously saved results, which are loaded for postprocessing purposes.

The advantage of the latter use is that it is not always clear, at the beginning of a simulation, which subdomains are of interest. Using the postprocessing feature, you can easily extend or modify the initial sets of extractors and sensors to further investigate the simulation results without having to rerun the entire FDTD simulation, which is generally time consuming.

Plots

Field values and material parameters can be output to either a tensor grid or a mixed-element grid. In both cases, you can output the data to either the entire grid or only a subdomain. Subdomains can be specified directly by providing the coordinates of the two opposing corners of a box. The corners with the minimum and maximum values for all coordinate axes are denoted by `BoxCorner1` and `BoxCorner2`, respectively. Alternatively, if the requested subdomain is a line in two dimensions or a plane in three dimensions, you can use a short form and define a line or plane perpendicular to one of the coordinate axes denoted by the keywords `PlaneX`, `PlaneY`, and `PlaneZ`. A plane is defined by a coordinate value for the axis to which it is perpendicular. In addition to specifying explicit coordinate values, you can specify `min` or `max`, which is interpreted as the minimum or maximum device extent along the corresponding coordinate axis.

Using the keyword `Region` in the `Plot` section is another option for specifying a subdomain. When outputting in tensor-grid data format, only a single region of the input tensor-grid file

can be specified. If output is requested on a mixed-element mesh, you can select several regions of the mixed-element grid file for plotting.

The exact meaning of the box corner and region depends on the grid type of the plot. For tensor plots, box corner and region refer to the input tensor grid. If the specified coordinates of a box corner do not coincide with a specific vertex of the tensor grid, the nearest vertex will be chosen instead. The dimension of the subdomain can be lower than that of the input tensor grid. Contrary to mixed-element plots, the resulting plot file only contains the specified subdomain. A typical example is a two-dimensional cut through a three-dimensional device structure.

For large (in terms of cell number) tensor meshes, visualization can be challenging, and plotting only the surface data may be a better option. In 3D device structures, the keyword `Domain` allows you to switch between volume and surface plots. For the latter, you can select explicitly certain faces of the domain using the keyword `Sides`.

For tensor plots, specifying the keyword `Region` in `Quantity` enables the visualization of the region information with the simulation results, for example:

```
Quantity = { AbsElectricField, AbsMagneticField, Region }
```

NOTE The keyword `Region` can appear as a command in the `Plot` or `Extractor` section or as a keyword in the list of `Quantity`. The former restricts the plotting area to a region, and the latter instructs EMW to include region information in the plot file.

Since a 2D tensor plot is supported only in `xy` format, when making 2D cuts from a 3D simulation, the coordinate systems are transformed using the rules listed in [Table 7](#).

Table 7 Coordinate system transformation rule for 2D cuts from a 3D simulation

Cut	Transformation rule
x-cut	Y (3D) -> X (2D) Z (3D) -> Y (2D) X (3D) -> Z (2D)
y-cut	Z (3D) -> X (2D) X (3D) -> Y (2D) Y (3D) -> Z (2D)
z-cut	X (3D) -> X (2D) Y (3D) -> Y (2D) Z (3D) -> Z (2D)

8: Extracting and Visualizing Results

Plots

NOTE Only the spatial coordinates follow this rule: The sub-indices of a vector quantity are unchanged when making a 2D cut. For example, the field components `AbsElectricFieldX`, `AbsElectricFieldY`, and `AbsElectricFieldZ` in the 3D plot are unchanged in the 2D x-cut, y-cut, and z-cut.

NOTE When `Region` is specified in `Quantity`, `Domain=Surface` is disallowed for visualizing 2D surface plots. To obtain 2D plots with region information in 2D simulations, `Region` in `Quantity` and `Domain=Volume` are specified in the `Plot` or `Extractor` section. To obtain 2D plots with region information in 3D simulations, specify `Region` in `Quantity`, `Domain=Volume`, and a boxed 2D region in the `Plot` or `Extractor` section.

Plotting the results on an arbitrary mixed-element mesh is triggered by specifying the corresponding grid file in the `Plot` section, using the keyword `GridFile`. For mixed-element plots, `BoxCorner` and `Region` refer to the grid file of the respective `Plot` section; whereas, specifying a plane is not supported. If a subdomain has been specified, the plot quantities are interpolated between the input tensor grid and the mixed-element grid for overlapping vertices. The values of the remaining vertices are set to zero.

Another group of keywords, which apply to both tensor and mixed-element plots, controls when data is plotted. A time interval during which plotting is active can be specified by either the absolute time (in seconds) or the number of time steps. The corresponding keywords are `StartTime`, `EndTime` or `StartTick`, `EndTick`. How often a plot file is generated is determined by the value of the keyword `TickStep`. If neither limit of the interval is specified, plotting is disabled and only a final plot at the end of the simulation is created. Whether a final plot is generated is controlled by the keyword `FinalPlot` whose default value is `yes`.

The file name for the plots is composed of the `Name` of the `Plot` section, the tool specific file suffix `em1`, and a running number if more than one plot file is written.

A list of supported plot quantities can be found in [Appendix A on page 99](#).

The following example shows two typical tensor `Plot` sections and a mixed-element `Plot` section:

```
Plot {
  Name = "box"
  Quantity = {AbsElectricField, AbsMagneticField, ElectricConductivityXX}
  BoxCorner1 = {min, min, 0}
  BoxCorner2 = {max, max, 4.5}
  StartTick = 500
  EndTick = 10000
```

```

    TickStep = 100
    FinalPlot = no
}

Plot {
    Name = "X-Normal-Cut"
    Quantity = {AbsElectricField, AbsMagneticField, ElectricConductivityXX}
    PlaneX = 1
    StartTick = 500
    EndTick = 10000
    TickStep = 100
    FinalPlot = no
}

Plot {
    Name = "mixed-element-plot"
    Quantity = {AbsElectricField, AbsMagneticField, Region}
    GridFile = "mixed-element-grid.tdr"
    Region = {"substrate", "center-box"}
}

```

Monitors

Monitors are used to probe field values at specific tensor-grid points in the device structure. Similar to plots and sensors, it is possible to control when fields are probed during the simulation using the keywords `StartTick/Time`, `EndTick/Time`, and `TickStep/Frequency`. Monitors can also be used to observe the convergence behavior at certain locations in the device. The computational cost of monitors is much lower than that of plots because, typically, only a limited number of points are probed. The probed field values along with the coordinates of their corresponding location are written to the `ResultFile` specified in the `Globals` section.

The locations to monitor are specified as a list of coordinate vectors as shown in the following example:

```

Monitor {
    Name = "monitor"
    Location = { {0.5, 2, 0.1}, {0.4, 3, 0.5} } # [um]
    Quantity = { AbsElectricField, CplxEMField }
    TickStep = 100
}

```

The quantity `CplxEMField` is an alias for the real and imaginary parts of all electromagnetic field components. However, it is also possible to list only specific field components such as `RealElectricFieldX`. For a complete list of supported quantities, see [Monitor on page 115](#).

Extractors

Extractors compute the quasi-monochromatic power flux density, the absorbed photon density, and the charge carrier generation rates assuming a quantum yield of 1 in absorbing semiconductor or metal media. A time-harmonic excitation signal is a prerequisite for the application of extractors. Therefore, extractors are only valid with a time-harmonic excitation signal and a steady-state solution.

NOTE The simulation must be performed until a time-harmonic state is reached with sufficient accuracy (a detector can be used for this purpose; see [Terminating Simulations on page 59](#)) before the specified extractor quantities are computed.

The absorbed photon density and carrier generation rate are computed from the intensity distribution and the electromagnetic material parameters as outlined here.

Output data is computed on the native FDTD tensor grid and can be written either to a tensor-grid file or a mixed-element grid file using linear finite-element interpolation. In both cases, it is possible to extract the required quantities only on a subdomain of the entire grid by using the keywords `Region`, or `BoxCorner1`, `BoxCorner2`, or `PlaneX`, `PlaneY`, `PlaneZ` as described in [Plots on page 64](#). Unless a mixed-element grid file is given as `GridFile` in the `Extractor` section, output is generated in the tensor-grid format with the same discretization as the input tensor-grid file specified in the `Globals` section.

NOTE Specifying a tensor-grid file using `GridFile` is not supported.

When extracting quantities to a mixed-element grid, the quantities must be interpolated from the native FDTD tensor grid. The interpolation can be controlled with the keyword `Interpolation`. The options `Standard` and `Simple` stand for different variants of bilinear interpolation; whereas, `Conservative` employs a special algorithm [1] that conserves the spatial integral of the interpolated quantity.

The following assumptions are made in the computation of the absorbed photon density and the carrier generation rate: When light propagates in an absorbing medium with complex refractive index $n = n' + in'' = \sqrt{\epsilon}$, the corresponding \mathbf{k} -vector also becomes complex, being given by:

$$\mathbf{k}^2 = n^2 \mathbf{k}_0^2 = (n' + in'')^2 \mathbf{k}_0^2 = (\epsilon' + i\epsilon'') \mathbf{k}_0^2 \quad (32)$$

where \mathbf{k}_0 is the vacuum wave vector.

To model this behavior in EMW, a nonzero conductivity σ must be assigned to that medium. Since you also have:

$$k^2 = \omega^2 \epsilon \mu \left(1 + i \frac{\sigma}{\omega \epsilon} \right) = k_0^2 \mu_r \left(\epsilon_r + i \frac{\sigma}{\omega \epsilon_0} \right) \quad (33)$$

the complex refractive index is correctly modeled if you set:

$$\sigma = \frac{2\pi c_0 \epsilon_0 \epsilon''}{\lambda_0 \mu_r} \quad (34)$$

where λ_0 is the vacuum wavelength and c_0 is the vacuum speed of light. In the microscopic world, this can correspond to a *real* conductivity caused by free charge carriers (in metals) or to a conductivity caused by material polarization.

The intensity distribution is given by the time-averaged Poynting vector:

$$\mathbf{S}_{av} = \frac{1}{2} \Re(\mathbf{E} \times \bar{\mathbf{H}}) \quad (35)$$

where the complex quantities are found from the real field values at two different times under the time-harmonic state assumption. The absorbed power density at each point is computed as:

$$W = -\nabla \cdot \mathbf{S}_{av} = \frac{1}{2} \sigma |\mathbf{E}|^2 \quad (36)$$

With the photon energy given by $E_{ph} = h\nu$, the optical carrier generation rate G_{opt} can be computed as:

$$G_{opt} = \eta \frac{W}{E_{ph}} \quad (37)$$

where η is the quantum yield, which gives the average number of charge carriers generated by a single photon; η is assumed to be 1. The absorbed photon density is simply given by the absorbed power density divided by the photon energy. The absorbed photon density and optical generation rate are written to the output file in units of $s^{-1} cm^{-3}$, the absorbed power density is written in units of $W cm^{-3}$, and the power flux density is written in units of $W m^{-2}$.

You can obtain all available output quantities in a single extractor by using the keyword `Quantity` as follows:

```
Quantity = { AbsorbedPhotonDensity, OpticalGeneration, AbsorbedPowerDensity,
             PowerFluxDensity }
```

8: Extracting and Visualizing Results

Sensors

In addition, you can visualize the region information by using the keyword `Region` in the `Quantity` statement of the `Extractor` section as follows:

```
Quantity = { AbsorbedPhotonDensity, OpticalGeneration, AbsorbedPowerDensity,  
             PowerFluxDensity, Region }
```

NOTE The values for the absorbed photon density and optical generation are identical except in insulator regions where the latter is always zero, independent of the imaginary part of the CRI in that medium.

Sensors

In general, sensors compute some integral quantity based on the values of the electromagnetic field available on the simulation grid. Their results are written to a file whose name is specified using the keyword `ResultFile` in the `Globals` section. Time-averaged results are extracted by probing the time-harmonic state when using a harmonic excitation signal, or by performing Fourier transform when using a Gaussian excitation signal.

One of the basic inputs for a sensor is the specification of the integration domain. The type of geometry that is required depends on the sensor quantity of interest. Power flux density and photon flux density are integrated over a surface; while the integration domain of the absorbed photon density, absorbed power density, and optical generation is a volume defined by a box, a region, or a material of the tensor grid.

A box is defined by two corners whose coordinates are given in units of micrometers. The corners with minimum and maximum values for all three coordinate axes are called `BoxCorner1` and `BoxCorner2`, respectively. A surface is specified by additionally selecting one or more sides of a box. If no side is given, output is generated for all six sides. An easier way to define a surface that extends to the device boundaries is to specify a plane using the keywords `PlaneX`, `PlaneY`, and `PlaneZ`. A plane is defined by a coordinate value for the axis to which it is perpendicular. In addition to specifying explicit coordinate values, you can specify `min` or `max`, which is interpreted as the minimum or maximum device extent along the corresponding coordinate axis.

Time-averaged sensors support two computation modes, which can be controlled with the keyword `Mode`. In both modes, `Integrate` and `Average`, the surface or volume integral of the given quantity is computed. For `Average`, the integrated value is divided by the surface or volume of the integration domain.

The following examples show how to define an optical generation sensor and a power flux density sensor for two different regions, a box, and a plane:

```
Sensor {
  Name = "sens1"
  Quantity = OpticalGeneration
  Region = {"substrate","ambient"} # defined as box in Sentaurus Mesh
  BoxCorner1 = {0.5,0.5,1.5}
  BoxCorner2 = {0.9,0.9,2.9}
  Mode = {Integrate,Average}
}

Sensor {
  Name = "sens2"
  Quantity = PowerFluxDensity
  Region = {"substrate","ambient"} # defined as box in Sentaurus Mesh
  Sides = {Zmin, Zmax}
  BoxCorner1 = {0,0,min}
  BoxCorner2 = {1,1,max}
  Mode = {Integrate,Average}
}

Sensor {
  Name = "sens3"
  Quantity = PowerFluxDensity
  PlaneZ = 0.5
  Mode = {Integrate,Average}
}
```

NOTE Sensors whose integration domain is a surface support only box-like regions or materials; whereas, sensors computing a volume integral can have regions or materials with arbitrary shapes as input.

NOTE Instead of specifying an explicit coordinate value, you can specify `min` or `max`, which is interpreted as the minimum or maximum device extent along the corresponding coordinate axis.

Computation time for integration domains defined by regions or materials can result in longer runtimes. Therefore, specification of a box is preferable whenever applicable.

Using Multiple Domains in a Sensor

If more than one integration domain is specified, the keyword `Domains` controls how they are plotted:

- `Separate` (default): Plots the integration value for each domain separately.
- `United`: Plots one single integration value corresponding to the integration volume of the overall domain.
- `Intersecting`: Performs the integration only for the intersection of all specified domains.

NOTE Regions and materials as well as a box and a plane are mutually exclusive integration domains.

For example, to extract optical generation in the intersecting domains of a region "r" and a box specification b (see [Figure 9](#)), use:

```
Sensor {  
  Name = "GreenSensor"  
  Quantity = OpticalGeneration  
  Mode = {Integrate, Average}  
  Region = {"r"}  
  BoxCorner1 = {0,0,min}  
  BoxCorner2 = {1,1,max}  
  Domains = Intersecting  
}
```




Figure 9 Quantity extraction in limited region allows users to study absorption in intersecting regions

Nonaxis-Aligned Sensor

Power flux sensors also can be defined as nonaxis-aligned boxes (see [Figure 10](#)).




Figure 10 Nonaxis-aligned sensor showing dimensions and rotation angles

The box dimensions L_x , L_y , and L_z are defined by the keyword `BoxDimensions`. The center of the box is set by `BoxCenter`, and the orientation can be controlled by `RotationAngles = { θ , ϕ , ψ }`, where the angles correspond to the definition of the plane wave excitation angles (Theta, Phi, Psi) defined in [Figure 5](#) on page 48, when replacing E with x, H with y, and k with z.

For example, the syntax to place a sensor box centered at (1, 1, 5) is:

```
Sensor {
  Name = "NonAxisAlignedSensor"
  Quantity = PowerFluxDensity
  Mode = {Integrate}
  BoxDimensions = {1.0, 1.0, 0.2}
  BoxCenter = {1.0, 1.0, 5.0}
  RotationAngles = {45, 45, 0}
}
```

NOTE The nonaxis-aligned sensor is supported only for measuring power flux and in three dimensions.

Note that a second rotation matrix following [2] can be chosen by setting `CoordinateTransformation = Standard`:

$$\bar{\mathbf{R}}(\theta, \phi, \psi) = \bar{\mathbf{R}}(\theta, \phi)\bar{\mathbf{R}}(\psi) = \begin{bmatrix} \sin\phi & \cos\theta\cos\phi & \sin\theta\cos\phi \\ -\cos\phi & \cos\theta\sin\phi & \sin\theta\sin\phi \\ 0 & -\sin\theta & \cos\theta \end{bmatrix} \begin{bmatrix} \cos\psi & -\sin\psi & 0 \\ \sin\psi & \cos\psi & 0 \\ 0 & 0 & 1 \end{bmatrix} \quad (38)$$

Far Field

EMW supports the computation of the far field by a near-to-far-field transformation, which is based on the derivation described in [3][4]. The near field is the result of a single FDTD simulation and it is extracted in the scattered-field region. The calculated far-field intensity is represented as a function of the polar diffraction angle, θ , and the azimuthal diffraction angle, ϕ , as illustrated in Figure 11. To obtain the far-field power, the intensity can be integrated over a user-supplied solid angle. For device structures that are periodic in the x- and the y-direction, the diffraction modes for a given array size are computed *a priori* assuming that the array is periodic to infinity.




Figure 11 Illustration of polar plot for representation of far field

NOTE Far-field computation is supported only in three dimensions, and the main propagation direction of the incident light must be in the positive z-direction. The normal of the excitation plane must align with the z-axis.

For a scattering grating array, the angles for the backscattered modes in the far-field zone can be computed by momentum matching:

$$(k_{n,m})_x = (k^{\text{inc}})_x + n \frac{2\pi}{L_x} \quad (39)$$

$$(k_{n,m})_y = (k^{\text{inc}})_y + m \frac{2\pi}{L_y} \quad (40)$$

In Eq. 39 and Eq. 40, n and m denote the mode order with respect to the x-direction and the y-direction. k^{inc} corresponds to the wavevector of the incident light, and $k_{n,m}$ stands for the wavevector of the scattering mode of order n and m .

Eq. 39 and Eq. 40 also can be expressed in polar coordinates to obtain the polar and the azimuthal scattering angles, θ^{sca} and ϕ^{sca} , for each mode, which are among the output quantities of the far-field feature:

$$\frac{2\pi}{\lambda} \sin\theta^{\text{sca}} \cos\phi^{\text{sca}} = \frac{2\pi}{\lambda} \sin\theta^{\text{inc}} \cos\phi^{\text{inc}} + n \frac{2\pi}{L_x} \quad (41)$$

$$\frac{2\pi}{\lambda} \sin\theta^{\text{sca}} \sin\phi^{\text{sca}} = \frac{2\pi}{\lambda} \sin\theta^{\text{inc}} \sin\phi^{\text{inc}} + m \frac{2\pi}{L_y} \quad (42)$$

For the computation of the far field of a finite array of size (n_x, m_y) , the near field resulting from the FDTD simulation is replicated accordingly before the near-to-far-field transformation is applied. With increasing array size, the scattering angles of the *a priori* calculated modes will converge with the maxima of the far-field intensity in the polar plot.

In this limit, the relative diffraction efficiency η_{rel} of a mode defined as:

$$\eta_{\text{rel}} = \frac{P_{\text{mode}}}{P_{\text{total}}} = \frac{\int_{\Omega_{\text{mode}}} E \wedge H d\Omega}{\int_{\Omega_{\text{total}}} E \wedge H d\Omega} \quad (43)$$

where Ω denotes the solid angle, can be approximated by the maxima of the far-field modes:

$$\eta_{\text{rel}} = \frac{P_{\text{mode}}}{P_{\text{total}}} = \frac{S(\theta_{\text{mode}}^{\text{sca}}, \phi_{\text{mode}}^{\text{sca}})}{\sum_{\text{mode}_i} S(\theta_{\text{mode}_i}^{\text{sca}}, \phi_{\text{mode}_i}^{\text{sca}})} \quad (44)$$

In Eq. 44, $S(\theta, \phi)$ represents the time-averaged Poynting vector at the scattering angles θ and ϕ . Figure 12 on page 76 illustrates the computation of the relative diffraction efficiency using Eq. 43 and in the limit of an infinite array size using Eq. 44.

8: Extracting and Visualizing Results

Far Field




Figure 12 Illustration of computation of relative diffraction efficiency: (*left*) the power of a mode is computed by integrating over a solid angle given by the expansion of the mode and (*right*) in the limit of an infinite array size, the power of a mode is determined by the maximum value of the far-field intensity

Specifying the Far-Field Computation

The far-field computation can be performed at the end of the FDTD simulation similar to sensors and extractors, or in a postprocessing step in which a previously saved near field is loaded from a file. In both cases, the far-field computation and its output are controlled by the keywords of the respective `Farfield` section, which are described here. Information related to postprocessing only is given in [Postprocessing of Extractors, Sensors, and Far Field on page 80](#).

In its simplest form, a `Farfield` section requires only the specification of a name and a domain representing a plane in the near-field zone:

```
Farfield {
  Name = "farfield"
  BoxCorner1 = {0,0,0}
  BoxCorner2 = {2,3,0}
# OR
  Region = "near-field-plane"
}
```

This section will trigger the computation of the far field at the default distance of 1 mm from the near-field plane. As a result, the far-field intensity as a function of the polar and the azimuthal diffraction angles is written to a TDR file named `farfield_eml.tdr`. In addition, the output from the computation of the far-field modes, corresponding to an infinite array size,

and the integration of the far-field intensity over the entire hemisphere are saved in the `ResultFile` specified in the `Globals` section along with the output of the optional `Sensor` and `Detector` sections.

Additional keywords can be used to customize the abovementioned output. With `PolarRange` and `AzimuthalRange`, the plotting of the far-field intensity as a function of diffraction angles can be restricted to a smaller solid angle than the hemisphere, and the angular discretization can be controlled:

```
Farfield {
  ...
  PolarRange = {30, 70, 0.5}
  AzimuthalRange = {90, 180, 2}
}
```

The first two entries of the range list specify the minimum angle and the maximum angle of the interval, respectively, and the third entry determines the angular discretization using an equidistant step size. All numbers are given in degrees.

It is also possible to save xy plots of the far-field intensity given a constant polar or azimuthal angle as they tend to be more amenable to quantitative analysis. Such angular cuts can be specified by either a range or an explicit list of angles:

```
Farfield {
  ...
  PolarCutRange = {0, 90, 30}
  AzimuthalCutList = {0, 45, 90, 180, 270}
}
```

In the above example, the far-field intensity as a function of the azimuthal angle is plotted for the polar angles 0° , 30° , 60° , and 90° , where the entries of the range list are the minimum polar angle, the maximum polar angle, and the step size, respectively. In addition, the far-field intensity as a function of the polar angle is plotted for the azimuthal angles specified in `AzimuthalCutList`.

To compute the total far-field power by integrating the far-field intensity over the entire hemisphere, you can specify a list of limited integration ranges. Each range consists of six numbers where the first three and the last three numbers correspond to the azimuthal and the polar angle range including the step size, respectively:

```
Farfield {
  ...
  IntegrationRange = { {0, 10, 0.2, 0, 360, 0.5}, {30, 45, 0.4, 80, 100, 1.} }
}
```

8: Extracting and Visualizing Results

Far Field

This option can be useful to integrate over the expansion of a particular mode to obtain its power. The above example shows how integrating over mode (0, 0) and mode (0, 1) according to [Figure 12 on page 76](#) could look like.

NOTE The far-field computation is performed independently for each of the different output quantities. For example, the choice for `PolarRange` and `AzimuthalRange` does not affect the computation of the angular cuts or the integration of the far-field intensity to obtain the far-field power. This also implies that the computational effort scales with the number of output quantities requested, for example, the number of integration ranges, and their specific discretization.

For FDTD simulations with periodic boundary conditions in the lateral direction, the near-field domain can be replicated in both the x- and y-direction to better approximate the actual physical extension of the device structure for the far-field calculation. How many times the near-field domain is replicated in the respective coordinate direction is set using the keyword `ArraySize`:

```
Farfield {  
    ...  
    ArraySize = {10, 20} # {nx, my}  
}
```

The radial distance at which the far field should be computed is given by the `Radius` keyword.

For a complete list of supported keywords in the `Farfield` section and their descriptions, see [Farfield on page 109](#).

Visualizing Results of the Far-Field Computation

This section summarizes the various output quantities produced by the far-field computation. They are saved either in the TDR file specified in the `Farfield` section or in the general `PLT ResultFile` specified in the `Globals` section. The name of the TDR file is derived from the `OutputFilePrefix` specified in the `Globals` section and the `Farfield` section name.

Table 8 Polar plot of far-field intensity saved in TDR file

Quantity	Unit	Description
<code>AzimuthalAngle</code>	deg	Azimuthal diffraction angle.
<code>FarfieldIntensity</code>	Wsr^{-1}	Far-field intensity as a function of the azimuthal and polar diffraction angles.

Table 8 Polar plot of far-field intensity saved in TDR file (Continued)

Quantity	Unit	Description
FarfieldIntensityMask	1	Auxiliary field indicating for which vertices the far-field intensity has actually been computed given the AzimuthalRange and the PolarRange selected in the Farfield section. All other vertices are assigned a zero default value.
PolarAngle	deg	Polar diffraction angle.

Table 9 Polar cuts saved in PLT file

Quantity	Unit	Description
AzimuthalAngle	deg	Azimuthal angle.
FarfieldIntensity_<float>deg	Wsr ⁻¹	Far-field intensity as a function of the azimuthal angle for a constant polar angle of <float> degrees.

Table 10 Azimuthal cuts saved in PLT file

Quantity	Unit	Description
FarfieldIntensity_<float>deg	Wsr ⁻¹	Far-field intensity as a function of the polar angle for a constant azimuthal angle of <float> degrees.
PolarAngle	deg	Polar angle.

Table 11 Far-field power for specified integration ranges saved in PLT file

Quantity	Unit	Description
AzimuthalAngleCenter	deg	Center of the azimuthal angle range for the given integration range.
AzimuthalAngleWidth	deg	Width of the azimuthal angle range for the given integration range.
IntegrationRangeIndex	1	Index to identify the far-field power corresponding to a specified integration range. It follows the order of the list entries given for the IntegrationRange keyword. The list index starts with number 1. Index 0 stands for the entire hemisphere as the integration range, which is always computed even if IntegrationRange is not specified.
PolarAngleCenter	deg	Center of the polar angle range for the given integration range.
PolarAngleWidth	deg	Width of the polar angle range for the given integration range.
Power	W	Far-field power for the given integration range.

8: Extracting and Visualizing Results

Postprocessing of Extractors, Sensors, and Far Field

Table 12 Far-field modes for infinite array structure saved in PLT file

Quantity	Unit	Description
AzimuthalAngle	deg	Azimuthal scattering angle ϕ^{sca} for the given mode as defined in Eq. 41 and Eq. 42.
ModeIndex	1	Index to identify the far-field modes of an infinite array structure as defined in Eq. 41 and Eq. 42. The index is defined by linearizing the 2D mode order where n is the fast-running index and m is the slow-running index.
ModeOrderX	1	Mode order n defined in Eq. 41.
ModeOrderY	1	Mode order m defined in Eq. 42.
PolarAngle	deg	Polar scattering angle θ^{sca} for the given mode as defined in Eq. 41 and Eq. 42.
RelativeDiffractionEfficiency	1	Relative diffraction efficiency for the given mode according to Eq. 44.

Postprocessing of Extractors, Sensors, and Far Field

To use the postprocessing feature of extractors, sensors, and the far field, the required underlying data must be saved in a file at the end of the FDTD simulation. This file can be loaded later by EMW to apply extractors, sensors, and the far-field computation without having to rerun the FDTD simulation, and it does not require an EMW license.

The quantities required for the postprocessing of extractors and sensors are `AbsorbedPhotonDensity` and `PowerFluxDensity`.

The syntax for saving a general results file for extractors and sensors is:

```
Save {
  Name = "n@node@_save"
  Quantities = {AbsorbedPhotonDensity, PowerFluxDensity}
  # domain specification (default entire device)
  BoxCorner1 = {0,0,0}
  BoxCorner2 = {4,6,8}
  # or
  Region = {"substrate"}
}
```

NOTE The keyword `Region` is not a supported entry for `Quantities` because the region information is saved by default in the general results file.

The postprocessing feature for the far-field computation requires only the quantity `CplxEMField` to be saved, which is an alias for the datasets `RealElectricField`, `ImagElectricField`, `RealMagneticField`, and `ImagMagneticField` to be written to the TDR file. For the reflected near-field, it is typically sufficient to save the quantity `CplxEMField` on a single plane in the near-field zone. However, at the expense of higher memory consumption and disk space usage, it is also possible to save the data in the entire 3D domain or a subdomain thereof, to allow for the selection of arbitrary near-field planes during postprocessing.

The syntax for saving a results file for far-field computation in postprocessing mode is:

```
Save {
  Name = "n@node@_save"
  Quantities = CplxEMField
  # plane at z=0 in near-field zone
  BoxCorner1 = {0,0,0}
  BoxCorner2 = {4,6,0}
  # or entire domain
  BoxCorner1 = {0,0,-4}
  BoxCorner2 = {4,6,8}
  # or
  Region = "near-field-region"}
}
```

The `Extractor`, `Sensor`, and `Farfield` sections can be specified at the same time during postprocessing, but since only one `LoadFile` can be read, the data therein must contain all the required quantities in a domain that includes all the domains specified in the different sections.

A `Save` section is like an `Extractor` section, however, it only supports `AbsorbedPhotonDensity`, `IncoherentAbsorbedPhotonDensity` (exclusively for incoherent FDTD simulations), `PowerFluxDensity`, and `CplexEMField` as `Quantities`. Further quantities allowed in extractors and sensors can be derived from those base quantities during postprocessing.

The command file used for postprocessing consists of a mandatory `Globals` section and the optional `Sensor`, `Extractor`, and `Farfield` sections:

```
Globals {
  OutputFilePrefix = "n@node@_"
  LoadFile = "n@node@_save_eml.tdr"
  ResultFile = "eml.plt"
}

Sensor {...}

Extractor {...}

Farfield {...}
```

8: Extracting and Visualizing Results

Discrete Fourier Transform

NOTE If the `Globals` section contains the keyword `LoadFile`, no other sections apart from `Globals`, `Sensor`, `Extractor`, and `Farfield` are allowed.

NOTE For details about the `OutputFilePrefix` keyword, see [Globals on page 113](#).

Discrete Fourier Transform

This section presents an overview of the discrete Fourier transform (DFT) feature that is implemented in EMW. A major motivation of the DFT is to obtain frequency responses at multiple frequencies from a single transient simulation. After obtaining electrical and magnetic fields at multiple frequencies, by executing the DFT from the time-domain simulation results, secondary quantities such as photon flux density are calculated at these frequencies of interest. This section covers the basic theory, practical considerations, and limitations of the DFT.

On-the-Fly DFT

Suppose $g(\mathbf{r}, t)$ represents the space- and time-dependent field values in the FDTD simulation, where $\mathbf{r} = (x, y, z)$ and $g = E_x, E_y, E_z, H_x, H_y, H_z$. Since the DFT in EMW is unrelated to spatial coordinates, the space-dependent variable \mathbf{r} can be omitted from the function g in the following derivation without loss of generality.

The continuous-time Fourier transform of $g(t)$ is:

$$G(\omega) = \int g(t) \exp(-i\omega t) \quad (45)$$

where $\omega = 2\pi f$. Within the FDTD framework, the above integration is approximated by the discrete-time Fourier transform:

$$G(\omega) = \sum_{n=0}^{N-1} g(n\Delta t) \exp(-i\omega n\Delta t) \quad (46)$$

During the FDTD simulation, the field value $g(t)$ is accumulated on the fly from the first time step at $t = 0$ until the last time step at $t = (N-1)\Delta t$.

The resolution of the discrete spectrum, that is, Δf , depends on both the number of DFT points (N) and the FDTD time step (Δt) by:

$$\Delta f = \frac{1}{N\Delta t} \quad (47)$$

Since the time step Δt is limited by the stability (Courant) criteria, the only way to increase the spectral resolution is to increase the number of time steps N .

Defining the DFT Wavelength Table

Light is often described in wavelengths instead of frequencies in optical simulations. Therefore, the DFT section in EMW defines a wavelength table for extracting the DFT fields. The DFT wavelength table is defined by:

$$\{\lambda | \lambda = \lambda_{\min} + l\Delta\lambda, \Delta\lambda = (\lambda_{\max} - \lambda_{\min}) / (N_{\lambda} - 1), 0 \leq l < N_{\lambda}\} \quad (48)$$

The wavelength resolution $\Delta\lambda$ is calculated from the user-defined input `MinWavelength` (λ_{\min}), `MaxWavelength` (λ_{\max}), and `NumberOfWavelengths` (N_{λ}).

Then, the corresponding DFT frequency table is:

$$\{f^{\text{tab}}\} = c_0 / \{\lambda\} \quad (49)$$

where c_0 is the vacuum speed of light.

NOTE In EMW, any wavelength-related keyword refers to the wavelength in vacuum.

The spectral resolution of the DFT frequency table may be different from that of the on-the-fly DFT. However, the former cannot be higher than the latter in order to obtain distinctive fields, that is, $\min(\Delta f^{\text{tab}}) \geq \Delta f$.

To access the DFT field $G(\omega)$ for a specific wavelength or for a range of wavelengths, different keywords can be used:

- `WavelengthList`: Specifies a comma-separated list of wavelengths from the wavelength table defined in the DFT section.
- `WavelengthRange`: Specifies a wavelength interval that includes at least one wavelength from the wavelength table defined in the DFT section. The interval boundaries do not have to coincide with any entry of the wavelength table.

The wavelengths specified using the keyword `WavelengthList` must match the wavelengths of the DFT wavelength table. Depending on the discretization of the wavelength table, wavelength entries with several digits after the decimal point may exist, and an exact match depends on the applied numeric precision. Therefore, the numeric precision can be controlled using the keyword `WavelengthPrecision`.

8: Extracting and Visualizing Results

Discrete Fourier Transform

For a wavelength λ_1 specified in `WavelengthList` to be considered an exact match with a wavelength λ_i from the DFT wavelength table, the following condition must be fulfilled, where p is the value given for `WavelengthPrecision`:

$$|\lambda_1 - \lambda_i| < 0.5 \times 10^{-p} \quad (50)$$

The keywords `WavelengthList`, `WavelengthRange`, and `WavelengthPrecision` can be specified in the `Plot`, `Extractor`, and `Sensor` sections for DFT simulations. If both `WavelengthList` and `WavelengthRange` are specified at the same time, the union of wavelengths is selected. The selected wavelengths can be only a subset of the table defined in [Eq. 49, p. 83](#). In such a case, EMW automatically calculates for only the selected wavelengths to save memory and computation time.

For examples using the keywords `WavelengthList` and `WavelengthRange`, see [EMW Syntax on page 86](#).

NOTE For DFT simulations, you must specify `WavelengthList` or `WavelengthRange` for extractors and sensors. Specifying neither of them in a `Plot` section selects the regular non-DFT field of the transient simulation with excitation wavelength as specified in the `Excitation` section if it exists or the wavelength corresponding to the automatically computed frequency given in [Eq. 57, p. 87](#).

Normalizing Field Values

When the input signal is a sinusoid, its Fourier-transformed input spectrum is the sum of two delta functions. Since EMW deals only with linear materials (therefore, a linear system), the output spectrum consequently consists of delta functions.

It only makes sense to extract DFT fields at the frequency of the sinusoid f_c :

$$F[\cos[2\pi f_c(t-t_0)]] = \frac{1}{2} [e^{-i2\pi t_0(f-f_c)} \delta(f-f_c) + e^{-i2\pi t_0(f+f_c)} \delta(f+f_c)] \quad (51)$$

However, the output spectrum must be scaled by $e^{-i2\pi t_0(f-f_c)}/2$ to obtain the same result as in the non-DFT simulation at $f = f_c$.

When the input signal is a transient Gaussian pulse, the input spectrum is a Gaussian function with its center shifted to the modulation frequency f_c :

$$F \left[e^{-\frac{(t-t_0)^2}{2\sigma^2}} \cos(2\pi f_c t) \right] = \sqrt{\frac{\pi\sigma^2}{2}} \left[e^{-i2\pi t_0(f-f_c)} e^{-2[\pi\sigma(f-f_c)]^2} + e^{-i2\pi t_0(f+f_c)} e^{-2[\pi\sigma(f+f_c)]^2} \right] \quad (52)$$

where t_0 and σ are the delay and the full width at half maximum (FWHM), respectively. From the scaling property of the Fourier transform, the narrower the time-domain Gaussian pulse, the wider its spectrum. The shape of the spectrum can be designed by adjusting the FWHM.

The spectrum of a Gaussian pulse has its maximum at the modulation center frequency. The energy decays rapidly as the frequency shifts away from the center frequency.

To make the DFT useful for broadband simulation, the field values, the power flux densities, and the optical generation must be normalized by the magnitude of the input spectrum.

This normalization procedure ensures that the input power is the same for every frequency component, and EMW performs this automatically. What you obtain from the simulation is the normalized spectrum $G(\omega)/G_{\text{input}}(\omega)$ instead of $G(\omega)$. In an FDTD simulation, the excitation waveform may not be exactly sinusoidal or Gaussian, so the input spectrum $G_{\text{input}}(\omega)$ is obtained from on-the-fly DFT instead of the above analytic formulas.

Downsampling of DFT

In many practical cases, the sampling frequency intrinsic to FDTD ($1/\Delta t$) is much larger than the maximum DFT frequency (f_{max}), while the Nyquist–Shannon sampling theorem requires $f_{\text{sample}} > 2f_{\text{max}}$. Based on this theorem and anti-aliasing considerations, consider a downsampling factor D such that $1/(D\Delta t) > 4f_{\text{max}}$ or $D < \lambda_{\text{min}}/(4c_0\Delta t)$. Eq. 46, p. 82 is rewritten as:

$$G(\omega) = \sum_{\tilde{n}=0}^{\lfloor \frac{N-1}{D} \rfloor} g(\tilde{n}D\Delta t) \exp(-i\omega\tilde{n}D\Delta t) \quad (53)$$

where $\lfloor \dots \rfloor$ denotes round towards zero. During the FDTD simulation, the field value $g(t)$ is accumulated on the fly by a time step of $D\Delta t$. If D is large (for example, greater than 100), downsampling will significantly reduce the computation time for the DFT calculation without the loss of accuracy.

Limitation of Single-Frequency Periodic Boundary Condition

The limitation on broadband simulation mainly comes from the single-frequency periodic boundary condition (PBC). For the sine–cosine method, the fields are copied from one periodic boundary to another with a phase shift that is dependent on the frequency.

8: Extracting and Visualizing Results

Discrete Fourier Transform

Suppose $S_{x_{\min}}$ and $S_{x_{\max}}$ are a pair of periodic boundaries. The following relationship is enforced to ensure the periodicity in the x-direction:

$$g(\mathbf{r}, t)|_{\mathbf{r} \in S_{x_{\min}}} = e^{-ik_x(x_{\max} - x_{\min})} g(\mathbf{r}, t)|_{\mathbf{r} \in S_{x_{\max}}} \quad (54)$$

where:

- $k_x = \hat{x} \cdot \hat{k} 2\pi f_c / v$ is the x-component of the wave vector.
- $g = E_x, E_y, E_z, H_x, H_y, H_z$.
- v denotes the speed of light in the excitation medium.

Since the phase shift $k_x(x_{\max} - x_{\min})$ depends on the modulation (or center) frequency f_c of a frequency-shifted Gaussian pulse, it is only constant at f_c . At the other frequencies away from f_c , the excitation component must assume different incident angles for the PBC to maintain the same constant phase shift that was computed at f_c . Therefore, a broadband Gaussian excitation is equivalent to the sum of excitations with different frequencies and different incident angles.

For a structure that is doubly periodic in the x- and y-directions, suppose the incident plane is the x-plane, that is, $k_y = 0$, and the DFT frequency is f . By phase-matching, you find the incident angle associated with the DFT frequency is $\alpha = \sin^{-1}[\sin \alpha_c(f_c/f)]$. Similarly, if the incident plane is the y-plane, that is, $k_x = 0$, the incident angle associated with the DFT frequency is $\beta = \sin^{-1}[\sin \beta_c(f_c/f)]$. However, when the incident plane is neither the x-plane nor the y-plane, the broadband injection angles (θ, ϕ) must be solved by the following nonlinear equations:

$$\begin{cases} \sin \theta \cos \phi = (f_c/f) \sin \theta_c \cos \phi_c \\ \sin \theta \sin \phi = (f_c/f) \sin \theta_c \sin \phi_c \end{cases} \quad (55)$$

When $\theta = \theta_c = 0$, the above equations hold for any DFT frequency f . Therefore, the PBC is independent of the frequency at normal incidence. In the case of normal incidence, it is unnecessary to calculate broadband injection angles even if the signal is broadband.

EMW Syntax

To set up a DFT wavelength table with 10 wavelengths, use:

```
DFT {
  MinWavelength = 350      # nm
  MaxWavelength = 750     # nm
  NumberOfWavelengths = 10
}
```


To extract DFT fields for the above wavelength table, use:

```
Plot/Extractor/Sensor {
  ...
  WavelengthRange = {250, 500} # 350, 394.44, 438.89, 483.33 nm
}

Plot/Extractor/Sensor {
  ...
  WavelengthList = {750, 394, 528} # 750, 394.44, 527.78 nm
}
```

NOTE Parentheses are used to define an interval, and braces are used to define a list.

If the DFT section is specified, you must use a pulsed excitation by specifying `Signal=Gauss` in the `PlaneWaveExcitation` section or the `TruncatedPlaneWaveExcitation` section (see [Temporal Dependency on page 53](#)). In this case, EMW automatically calculates the pulse width, the frequency, and the delay as follows:

$$\sigma = 2\sqrt{\ln 2} / \left(\pi c_0 \left(\frac{1}{\lambda_{\min}} - \frac{1}{\lambda_{\max}} \right) \right) \quad (56)$$

$$f = \frac{c_0}{2} \left(\frac{1}{\lambda_{\min}} + \frac{1}{\lambda_{\max}} \right) \quad (57)$$

$$t_0 = 3\sigma \quad (58)$$

If $\lambda_{\min} = \lambda_{\max}$, `NumberOfWavelengths` must be 1, and:

$$\sigma = \frac{\lambda_{\min}}{c_0} = \frac{\lambda_{\max}}{c_0} \quad (59)$$

$$f = \frac{c_0}{\lambda_{\min}} = \frac{c_0}{\lambda_{\max}} \quad (60)$$

In [Eq. 56](#), [Eq. 57](#), [Eq. 59](#), and [Eq. 60](#), λ_{\min} , λ_{\max} , and c_0 denote `MinWavelength`, `MaxWavelength`, and the vacuum speed of light, respectively. If you specify σ using the keyword `Sigma`, or f using the keyword `Frequency` or `Wavelength`, or t_0 using the keyword `Delay`, EMW uses the user-defined value instead of the automatically calculated value.

To specify the downsampling rate of DFT, use:

```
DFT {
  ...
  DownSampling = <integer>
}
```

8: Extracting and Visualizing Results

References

If the user-specified downsampling rate is less than $\lambda_{\min}/(4c_0\Delta t)$, the user-specified value will be used. If the user-specified downsampling rate is greater than $\lambda_{\min}/(4c_0\Delta t)$, an error message will be issued because DFT accuracy will not be guaranteed. If the `DownSampling` keyword is not specified, EMW will automatically use $\lambda_{\min}/(4c_0\Delta t)$ as the downsampling rate.

NOTE Do not use the DFT with the CRI library. Instead, specify `epsilon_r` and `sigma` for each material in the parameter file, or consider using dispersive models (see [Dispersive Model Parameters on page 37](#)).

References

- [1] F. Alauzet and M. Mehrenberger, “P¹-conservative solution interpolation on unstructured triangular meshes,” *International Journal for Numerical Methods in Engineering*, vol. 84, no. 13, pp. 1552–1588, 2010.
- [2] J. A. Kong, *Electromagnetic Wave Theory*, Cambridge, Massachusetts: EMW Publishing, 2008.
- [3] A. Taflove and S. C. Hagness, *Computational Electromagnetics: The Finite-Difference Time-Domain Method*, Boston: Artech House, 3rd ed., 2005.
- [4] C. A. Balanis, *Advanced Engineering Electromagnetics*, New York: John Wiley & Sons, 1989.

CHAPTER 9 Parallelization

This chapter describes parallelization of EMW using multithreading and the message passing interface.

Overview

EMW supports parallel finite-difference time-domain (FDTD) computation for wave propagation, radiation, and scattering on both shared-memory parallelization (SMP) and distributed processing (DP) systems. The SMP and DP systems are usually referred as multicores and clusters, respectively. EMW performs differently on SMP and DP systems, depending on the computer architectures, the bandwidth of interconnects and memory buses, and the sizes and domain decomposition of the problems to be solved.

Shared-Memory Parallelization

In general, the number of threads to be used in an EMW simulation can be specified either in the `Globals` section of the command file or by an environment variable. If both are specified, the value in the command file overrides the value of the environment variable. The following two examples illustrate the use of both options to set the number of threads to 2.

The specification in the `Globals` section is:

```
Globals {  
    ...  
    NumberOfThreads = 2    # or maximum  
    ...  
}
```

The specification using a UNIX environment variable (for example, C shell syntax) is:

```
setenv EMW_NUMBER_OF_THREADS 2
```

The environment variable also can be used to set the number of threads to the maximum available on a given machine:

```
setenv EMW_NUMBER_OF_THREADS maximum
```

By default, the number of threads is set to 1.

Parallelization of Message Passing Interface

Distributed computation of FDTD can be activated using the message passing interface (MPI) [1] of EMW. EMW uses the MPICH library for MPI implementation [2]. In this methodology, domain decomposition is used, and each subdomain problem of FDTD is distributed to be solved by separate processes.

The best performance is achieved if you use cluster machines with special fast interconnections between the machines. The MPI job also can be distributed over a network of machines, but the speedup will be limited by the speed and bandwidth of the network connections between the machines.

Domain Decomposition

An automatic domain decomposition (ADD) algorithm has been implemented in EMW to decompose both 2D and 3D structures for optimal performance of the code in parallel mode.

NOTE ADD applies only to the DP mode of EMW (denoted as EMW MPI).

The algorithm chooses an integer decomposition of the number of processes to be as close as possible to the product of the square and cubic roots for 2D and 3D structures, respectively.

The scalability degrades when the number of processes is a large prime number. The best performance can be achieved for 2D and 3D structures when the number of processes can be expressed as a square and a cubic of an integer, respectively.

The minimum number of cells in each direction of each subdomain is set to ten except for the degenerated dimension in 2D structures. The ADD algorithm also does not decompose the simulation domain in the convolutional perfectly matched layer (CPML). Therefore, the number of processes cannot be arbitrarily large for a given problem. If the ADD algorithm cannot find a suitable decomposition, EMW terminates.

For a simulation domain that has a greater number of cells in one of the Cartesian directions, a domain decomposition in this direction is possible to achieve better speedup than the ADD. To enforce ADD (default) or domain decomposition in the x-, y-, or z-direction only, use the following syntax:

```
Globals { ...  
    DomainDecomposition = Automatic | X | Y | Z  
}
```

Each decomposed subdomain is solved by one MPI process.

Installing and Using EMW MPI on DP Systems

Installing a distributed application is considerably more complex than installing its sequential or SMP version, because it requires an experienced administrator with expertise on Linux and networking.

You can try a preconfigured Linux cluster distribution such as Rocks before building a cluster [3].

Hardware and Software Setup

EMW MPI is available for Red Hat Enterprise Linux v6.6 and v7.1 on x86-64 platforms. All cluster nodes must be configured with a Synopsys QSC-compliant Linux distribution.

All nodes of the cluster should have the same software setup including the operating system version and EMW version. You should install EMW on a shared network drive that is accessible using the same path on all nodes. This configuration will reduce the sources of errors due to inconsistent software versions and configuration issues.

NOTE The cluster should have one head node that has more CPU power and RAM than the computing nodes, because the master process of EMW MPI requires maximum RAM for all computed results, and CPU power for not yet DP-parallelized portions of EMW MPI.

The overall speed of EMW MPI is limited by the slowest node and the communication bandwidth between nodes.

Licensing for SMP and DP Parallel Modes

Two different license features are available for running EMW in parallel mode. The type of license feature to be checked out depends on whether EMW is run in SMP mode, DP mode, or mixed DP and SMP mode.

SMP Parallel Mode

In SMP parallel mode, EMW first tries to check out a license for DP parallelization as it entitles the user to run the program with an unlimited number of threads. If it fails because the license is not available or already in use by another simulation, EMW will check out one license for SMP parallelization for every multiple of four threads specified by the user. The advantage of this order of license-checking is that DP licenses will be consumed first as they are not applicable to any other TCAD Sentaurus tools. In contrast, SMP licenses also are used by other tools such as Sentaurus Device and Sentaurus Process.

9: Parallelization

Parallelization of Message Passing Interface

DP Parallel Mode

Running EMW in DP parallel mode requires one license for DP parallelization for every multiple of four MPI processes. For example, an EMW simulation distributed over n nodes using 18 MPI processes will check out five licenses for DP parallelization.

Mixed DP and SMP Parallel Mode

Since one license for DP parallelization allows the use of an unlimited number of threads, the DP licensing scheme described in [DP Parallel Mode on page 92](#) also applies to the mixed DP and SMP parallel mode.

Controlling Parallel Licenses

The license checkout behavior described for the SMP and DP parallel modes can be controlled further by specifying, in the `Globals` section, the keywords `ParallelLicenses` and `UnavailableLicenseAction`. The former determines which licenses EMW is generally allowed to check out; whereas, the latter controls the behavior of EMW if none of the allowed licenses is available.

For `ParallelLicenses`, the options `MPI` (to select the `emwmpi` license) and `SMP` (to select the `sdevice-parallel` license) are supported. [Table 13](#) explains the options for the keyword `UnavailableLicenseAction`.

Table 13 Options if insufficient parallel licenses are available

Option	Description
<code>abort</code>	Terminate the simulation.
<code>reduce</code>	Reduce the number of threads used in SMP parallel mode to match the number of available parallel licenses.
<code>serial</code>	Continue the simulation in serial mode.
<code>wait</code>	Wait until enough parallel licenses become available.

For SMP simulations, the default values are:

```
ParallelLicenses = {MPI, SMP}
UnavailableLicenseAction = serial
```

For DP simulations, the default values are:

```
ParallelLicenses = {MPI}
UnavailableLicenseAction = abort
```

The following example shows how to avoid checking out an emwmpi license for an SMP parallel simulation and to terminate if the sdevice-parallel license is not available:

```
Globals {  
    ParallelLicenses = {SMP}  
    UnavailableLicenseAction = abort  
}
```

The ability to control the parallel license behavior can be useful, for example, when several users run Sentaurus Device and EMW parallel simulations using the same pool of licenses and start them through Sentaurus Workbench.

Installing Clusters

To install a cluster correctly:

1. Ensure the prerequisites for running EMW in DP mode are met:
 - a) SSH and Python are installed on each system and are available in the search path of each user.
 - b) Use a network file system for the installation and user directories, where the path will be the same on each system.
2. Install the TCAD Sentaurus distribution in the target directory on your network file system following the instructions in the *Synopsys® TCAD Installation Notes*.
3. Ensure each user has the proper environment settings to run TCAD Sentaurus, following the instructions in the *Synopsys® TCAD Installation Notes*.

Running EMW MPI on a Cluster

This section describes how to run EMW MPI on a cluster using plain Linux, MPI, and EMW commands. In its simple form, three steps are required to perform an EMW simulation in DP mode:

1. Set up SSH for password-less log-on to all required hosts.
2. Create the file `mpichhostfile.txt` with the list of required hosts. The master node must also be included in this file.
3. Run EMW using the command-line option `-mpi`.

The first step is required only once for each cluster; whereas, adapting the file `mpichhostfile.txt` may be necessary if additional or different computational resources are required for a specific simulation.

9: Parallelization

Parallelization of Message Passing Interface

At the end of this section, some information is given about support for cluster management systems.

Configuring SSH

EMW uses MPICH Hydra as the MPI process manager. As such, you must ensure that password-less `ssh` command invocations work from the head node to all computing nodes in a cluster.

Assuming a standard SSH installation and a shared home directory on all cluster nodes, this can be achieved by logging on to one of the cluster nodes as follows:

1. Generate a pair of authentication keys on the host:

```
ssh-keygen -t rsa
```

Do not enter a passphrase, and use the default file name.

2. Add the public key to the authorized keys:

```
touch ~/.ssh/authorized_keys
```

```
chmod 600 ~/.ssh/authorized_keys
```

```
cat ~/.ssh/id_rsa.pub >> ~/.ssh/authorized_keys
```

For alternatives, consult the SSH documentation.

By using the common UNIX commands `ssh` and `hostname`, verify that log-on without a password is possible by issuing `ssh <nodename> hostname` for each relevant node with the name as `<nodename>`. If necessary, answer the question about the *RSA key fingerprint* with `yes`.

Moreover, `ssh <nodename> hostname` should display the name of the cluster node without being asked for any passwords, passphrases, RSA keys, or any other input. Alternative configurations include:

- To avoid the question about *RSA key fingerprint*, the system administrator can provide you with a preconfigured `~/.ssh/known_hosts` file.
- Another option is to provide a suitable `/etc/ssh/known_hosts` file on every system.
- Use the command `ssh-keyscan` to collect the necessary keys.

For more information about SSH configurations, refer to the manuals of SSH and SSHD, or go to [\[4\]](#).

Creating the MPICH Host File

Create an `mpichhostfile.txt` file that lists the names of all the nodes of your cluster.

The machine file must not contain empty lines, for example:

```
$ cat ~/mpichhostfile.txt
node1:4
node2:4
node3:4
node4:4
```

In the above example, it is required that four MPI processes run on each of the four nodes. The total number of processes must be 16. If only a list of nodes is specified, the MPI process manager tries to divide the processes equally. For example, the following `mpichhostfile.txt` file is equivalent to that in the above example for a total of 16 MPI processes:

```
$ cat ~/mpichhostfile.txt
node1
node2
node3
node4
```

Automated Cluster Execution Using EMW Command-Line Option

After successful completion of the steps described in [Running EMW MPI on a Cluster on page 93](#) and [Configuring SSH on page 94](#), it is recommended to run EMW in DP mode using the command-line option `-mpi` either from the command line or through Sentaurus Workbench (see [Can I Run EMW MPI Through Sentaurus Workbench? on page 133](#)).

The following command is used to start EMW MPI from the command line:

```
$ emw -mpi -n <#processes> <command file>
```

This command will look for a host file in the following locations (in order of priority):

1. `./mpichhostfile.txt`
2. `$STDB/mpichhostfile.txt`
3. `$STROOT/tcad/$STRELEASE/lib/mpichhostfile.txt`

Alternatively, using the command-line option `-f <hostfile>`, you can specify a host file explicitly where `<hostfile>` stands for the name of the host file including its full path if it is not located in the current working directory:

```
$ emw -mpi -n <#processes> -f <hostfile> <command file>
```

9: Parallelization

Choosing Between Shared-Memory Parallelization and Distributed Processing

See [Creating the MPICH Host File on page 95](#) for the format of the host file.

The advantage of the automated cluster execution is that it manages MPI processes and the execution of `mpiexec.hydra` with the required command-line options, as outlined in [Cluster Execution Using Low-Level MPI Commands](#).

Cluster Execution Using Low-Level MPI Commands

In the following situations, it may be necessary to use low-level MPI commands to run EMW on a cluster:

- Access to a cluster is only granted through a cluster management system.
- Additional MPI options must be set that are not supported by the automated cluster execution using the EMW command-line option.
- Troubleshoot the MPI setup.

EMW uses MPICH [2] as an infrastructure for process management and communication between nodes.

A compiled version of MPICH is installed with TCAD Sentaurus in the installation directory `$(STROOT)/tcad/current/linux64/mpich/`, including binaries, man pages, and documentation as provided by MPICH.

To make MPICH available, you must configure the environment as follows:

- The paths to both EMW and MPICH must be included in the `$PATH` variable.
- Verify correct settings by executing `which emw` and `which mpiexec.hydra` on the command line. Ensure the `$PATH` variable does not point to LAM MPI, OpenMPI, and other MPI installations that may already exist on the system.
- MPICH requires Python version 2.3 or higher for execution. Use `python -V` to find the version of Python that comes first in the `$PATH` variable.

Choosing Between Shared-Memory Parallelization and Distributed Processing

In SMP systems, many cores share one set of memory. The operating system manages the distribution of multiple threads to the cores, and the multithreading is largely invisible to users. Threads are not bound to specific cores, and the number of threads can be greater than the number of cores on a node. However, when a simulation requires large amounts of memory and threads need to access memory modules belonging to different CPUs, the performance of SMP programs will be adversely affected because of the limited throughput of memory buses and cache thrashing.

To obtain the best performance on SMP systems, it is recommended to choose platforms with larger CPU caches and the latest memory bus architectures, such as AMD HyperTransport™ and Intel® QuickPath. Higher throughput memories such as DDR3 may help to improve the speedup on SMP systems.

DP systems consist of a number of individual computing nodes connected by a communication network. DP programs are managed by an MPI process manager, which is responsible for distributing the computing processes and their communication to hardware resources on the computing nodes. Best performance is achieved if each node executes a number of processes that is less than or equal to the number of its cores.

Alternatively, in the mixed DP and SMP mode, the best performance is achieved when the number of MPI processes (DP) equals the number of CPUs, and the number of threads (SMP) equals the number of cores per CPU.

In contrast to SMP programs, the scalability of DP programs is often good for a large number of nodes. If the size of the problem is sufficiently large, the communication (or data exchange) cost is much less than the computing cost for each subdomain, and DP programs definitely outperform SMP ones. However, solving a small problem by domain decomposition is not efficient because of the overhead of communication between MPI processes in the DP systems.

References

- [1] For more information about the Message Passing Interface Forum, go to <http://www.mpi-forum.org/>.
- [2] For more information, go to <http://www.mpich.org/>.
- [3] For more information, go to <http://www.rocksclusters.org/>.
- [4] For more information, go to <http://www.openssh.com/>.

9: Parallelization

References

APPENDIX A Commands

This appendix describes the command keywords available for use with Sentaurus Device Electromagnetic Wave Solver.

Boundary

This section is mandatory and can occur six times.

Table 14 Keywords of Boundary section

Keyword	Unit	Default value [range]	Description
AlphaMax = <float>	$\Omega^{-1} \text{m}^{-1}$	0.2	Maximum value of PML parameter alpha used in polynomial grading of PML tensor coefficient.
AlphaProfile = <float> { <float>, ... }	$\Omega^{-1} \text{m}^{-1}$	-	Profile of PML parameter alpha used in grading of PML tensor coefficient. The number of points of the profile must be double the size of the (PML) Thickness parameter.
KappaMax = <float>	1	15	Maximum value of PML parameter kappa used in polynomial grading of PML tensor coefficient.
KappaProfile = <float> { <float>, ... }	1	-	Profile of PML parameter kappa used in grading of PML tensor coefficient. The number of points of the profile must be double the size of the (PML) Thickness parameter.
OrderAlpha = <integer>	1	1	Order of polynomial grading for PML parameter alpha used in polynomial grading of PML tensor coefficient.
OrderKappa = <integer>	1	3	Order of polynomial grading for PML parameter kappa used in polynomial grading of PML tensor coefficient.
OrderSigma = <integer>	1	3	Order of polynomial grading for PML parameter sigma used in polynomial grading of PML tensor coefficient.

A: Commands
Boundary

Table 14 Keywords of Boundary section

Keyword	Unit	Default value [range]	Description
Sides = <identifier> { <identifier>, ... }	1	{ All }	Sides to which the boundary specification applies. Exclusive options are: <ul style="list-style-type: none"> • All • X • Xmin • Xmax • Y • Ymin • Ymax • Z • Zmin • Zmax
SigmaMax = <float>	$\Omega^{-1} \text{m}^{-1}$	-	Maximum value of PML parameter sigma used in polynomial grading of PML tensor coefficient. The default value is computed automatically from the grid spacing and refractive index.
SigmaProfile = <float> { <float>, ... }	$\Omega^{-1} \text{m}^{-1}$	-	Profile of PML parameter sigma used in grading of PML tensor coefficient. The number of points of the profile must be double the size of the (PML) Thickness parameter.
Thickness = <integer>	1	15	Thickness of PML boundary in terms of number of tensor-grid cells.
Type = <identifier>	1	Periodic Oblique	Type of boundary condition. Exclusive options are: <ul style="list-style-type: none"> • CPML • Higdon • Mur • PEC • Periodic • PeriodicOblique • PMC

CodeVExcitation

This section is optional and can occur only once.

Table 15 Keywords of CodeVExcitation section

Keyword	Unit	Default value [range]	Description
AmplitudeScaling = <float>	1	1	Scaling factor for electric field amplitude.
AnchorPoint1 = { <float>, <float>, <float> }	μm	-	Anchor point (of smallest coordinates) for the first data file.
AnchorPoint2 = { <float>, <float>, <float> }	μm	-	Anchor point (of smallest coordinates) for the second data file.
Delay = <float>	1	0	Number of signal periods before signal starts.
Frequency = <float>	s^{-1}	-	Signal frequency.
InputDataFile = "<string>" { "<string>", ... }	1	-	Names of two input data files from CODE V.
NRise = <float>	1	2	Number of signal periods before full amplitude is reached.
PhaseShift = <float>	deg	0	Linear phase shift for electric field.
Signal = <identifier>	1	Harmonic	Sets transient form of the signal. Exclusive options are: <ul style="list-style-type: none"> • Gauss • Harmonic
Wavelength = <float>	nm	-	Signal wavelength.

ComplexRefractiveIndex

This section is optional and can occur multiple times.

Table 16 Keywords of ComplexRefractiveIndex section

Keyword	Unit	Default value [range]	Description
CarrierDep = <identifier> { <identifier>, ... }	1	-	Controls carrier dependency of real and imaginary parts of complex refractive index. Exclusive options are: <ul style="list-style-type: none"> • Real • Imag
CRIModel = "<string>"	1	-	Name of user-provided complex refractive index model.
Extrapolate = <identifier>	1	No	Controls extrapolation behavior for interpolation of datasets in FieldDataFile specified in Globals section. Exclusive options are: <ul style="list-style-type: none"> • Yes • No
GainDep = <identifier> { <identifier>, ... }	1	-	Controls gain dependency of real part of complex refractive index. Exclusive options are: <ul style="list-style-type: none"> • RealLin • RealLog
IgnoreMaterials = <identifier>	1	No	Controls whether interpolation between vertices of different materials is permitted when loading datasets from FieldDataFile specified in Globals section. Exclusive options are: <ul style="list-style-type: none"> • Yes • No
Material = "<string>" { "<string>", ... }	1	-	Names of materials to which the complex refractive index specification applies.
Region = "<string>" { "<string>", ... }	1	-	Names of regions to which the complex refractive index specification applies.
TemperatureDep = <identifier> { <identifier>, ... }	1	-	Controls temperature dependency of real part of complex refractive index. Exclusive options are: <ul style="list-style-type: none"> • Real • Imag

Table 16 Keywords of ComplexRefractiveIndex section

Keyword	Unit	Default value [range]	Description
Type = <identifier>	1	Homogeneous	Controls type of complex refractive index distribution. Users can choose between a homogeneous (regionwise constant complex refractive index) and an inhomogeneous (complex refractive index may vary within a region) distribution, which is computed based on dependent data fields such as a temperature profile. Another option is to directly load an external complex refractive index profile. Exclusive options are: <ul style="list-style-type: none"> • Homogeneous • Inhomogeneous • FromFile
WavelengthDep = <identifier> { <identifier>, ... }	1	-	Controls wavelength dependency of real and imaginary parts of complex refractive index. Exclusive options are: <ul style="list-style-type: none"> • Real • Imag

Detector

This section is optional and can occur only once.

Table 17 Keywords of Detector section

Keyword	Unit	Default value [range]	Description
BoxCorner1 = { <float> min max, <float> min max, <float> min max }	μm	-	One of the two corners of a box that specifies the detector domain. Use min or max for the minimum or maximum device extents along the corresponding coordinate axis.
BoxCorner2 = { <float> min max, <float> min max, <float> min max }	μm	-	One of the two corners of a box that specifies the detector domain. Use min or max for the minimum or maximum device extents along the corresponding coordinate axis.
BreakOnError = <identifier>	1	Yes	Specifies whether the simulation stops if an error (for example, floating-point exception) is encountered during the simulation. Final Plot or Extractor sections will still be executed. Exclusive options are: <ul style="list-style-type: none"> • Yes • No

A: Commands
Detector

Table 17 Keywords of Detector section

Keyword	Unit	Default value [range]	Description
FailureOnUnreachedTolerance = <identifier>	1	Yes	Specifies whether the exit code of the program will be set to a nonzero value if the simulation has not reached the specified tolerance. Exclusive options are: <ul style="list-style-type: none"> • Yes • No
Frequency = <float>	s ⁻¹	-	Detector frequency. The default value is calculated from the excitation wavelength.
Region = "<string>"	1	-	Valid box or region name of the tensor grid where the detector is evaluated.
StartTick = <integer>	1	0	Number of tick steps when to start the detector evaluation.
StartTime = <float>	s	0	Simulation time when to start the detector evaluation.
StepX = <integer>	1	10	Detection is performed on every <integer>-th grid point in the x-direction only.
StepY = <integer>	1	10	Detection is performed on every <integer>-th grid point in the y-direction only.
StepZ = <integer>	1	10	Detection is performed on every <integer>-th grid point in the z-direction only.
Tolerance = <float>	1	0.001	The simulation is terminated when the maximum deviation is smaller than <float>.
Type = <identifier>	1	Periodic	Type of detector. Exclusive options are: <ul style="list-style-type: none"> • Periodic • Decayed

DFT

This section is optional and can occur only once.

Table 18 Keywords of DFT section

Keyword	Unit	Default value [range]	Description
DownSampling = <integer>	1	-	Downsampling rate of DFT.
MaxWavelength = <float>	1	-	End wavelength of the DFT wavelength table.
MinWavelength = <float>	1	-	Start wavelength of the DFT wavelength table.
NumberOfWavelengths = <integer>	1	-	Number of elements in the DFT wavelength table.

DispersiveMedia

This section is optional and can occur multiple times.

Table 19 Keywords of DispersiveMedia section

Keyword	Unit	Default value [range]	Description
DeltaK = <float>	1	0	Activate dispersive model for $k + \text{DeltaK} \geq n$.
ExcludeMaterial = "<string>" { "<string>", ... }	1	-	Names of materials to which dispersive medium specification does not apply.
ExcludeRegion = "<string>" { "<string>", ... }	1	-	Names of regions to which dispersive medium specification does not apply.
InterfaceAveraging = <identifier>	1	No	Controls whether interface averaging is granted for dispersive regions or materials specified in this section. Exclusive options are: <ul style="list-style-type: none"> • Yes • No
Material = "<string>" { "<string>", ... }	1	-	Names of materials to which the dispersive medium specification applies.

A: Commands
Extractor

Table 19 Keywords of DispersiveMedia section

Keyword	Unit	Default value [range]	Description
Model = <identifier>	1	-	Selects dispersive model. Exclusive options are: <ul style="list-style-type: none"> • Debye • Drude • DrudeLorentz • DrudeModLorentz • Lorentz • ModLorentz • SingleDipoleDebye • SingleDipoleDrude
ModelParameters = <identifier>	1	ComputeFromComplexRefractiveIndex	Specifies how dispersive model parameters are determined. Exclusive options are: <ul style="list-style-type: none"> • ComputeFromComplexRefractiveIndex • UserDefined
Region = "<string>" { "<string>", ... }	1	-	Names of regions to which the dispersive medium specification applies.

Extractor

This section is optional and can occur multiple times.

Table 20 Keywords of Extractor section

Keyword	Unit	Default value [range]	Description
BoxCorner1 = { <float> min max, <float> min max, <float> min max }	μm	-	One of the two corners of a box for which data must be extracted. Use min or max for the minimum or maximum device extents along the corresponding coordinate axis.
BoxCorner2 = { <float> min max, <float> min max, <float> min max }	μm	-	One of the two corners of a box for which data must be extracted. Use min or max for the minimum or maximum device extents along the corresponding coordinate axis.
GridFile = "<string>"	1	-	Name of mixed-element grid file for output data.
Interpolation = <identifier>	1	Standard	Way of interpolating extraction data from tensor grid to the mixed-element grid. Exclusive options are: <ul style="list-style-type: none"> • Standard • Simple • Conservative

Table 20 Keywords of Extractor section

Keyword	Unit	Default value [range]	Description
Name = "<string>"	l	-	Defines the name of the extractor, which also is used for the output file name by appending <code>_eml.tdr</code> .
PlaneX = <float> <identifier>	μm	-	Extractor domain specified as a line (in two dimensions) or a plane (in three dimensions) perpendicular to the x-axis. For <identifier>, use either <code>min</code> or <code>max</code> for the minimum or maximum device extents along the corresponding coordinate axis.
PlaneY = <float> <identifier>	μm	-	Extractor domain specified as a line (in two dimensions) or a plane (in three dimensions) perpendicular to the y-axis. For <identifier>, use either <code>min</code> or <code>max</code> for the minimum or maximum device extents along the corresponding coordinate axis.
PlaneZ = <float> <identifier>	μm	-	Extractor domain specified as a plane in three dimensions perpendicular to the z-axis. For <identifier>, use either <code>min</code> or <code>max</code> for the minimum or maximum device extents along the corresponding coordinate axis.

A: Commands
Extractor

Table 20 Keywords of Extractor section

Keyword	Unit	Default value [range]	Description
Quantity = <identifier> { <identifier>, ... }	1	-	Specifies the quantities to extract. Exclusive options are: <ul style="list-style-type: none"> AbsorbedPhotonDensity AbsorbedPowerDensity OpticalGeneration PowerFluxDensity AbsElectricField CplxEMField CplxElectricField RealElectricField RealElectricFieldX RealElectricFieldY RealElectricFieldZ ImagElectricField ImagElectricFieldX ImagElectricFieldY ImagElectricFieldZ CplxMagneticField AbsMagneticField RealMagneticField RealMagneticFieldX RealMagneticFieldY RealMagneticFieldZ ImagMagneticField ImagMagneticFieldX ImagMagneticFieldY ImagMagneticFieldZ Region
Region = "<string>" { "<string>", ... }	1	-	Regions for which data must be extracted. If not specified, data for the whole simulation domain will be extracted.
ScatteredFieldOnly = <identifier>	1	No	Specifies whether the extractor involves only scattered fields. Exclusive options are: <ul style="list-style-type: none"> Yes No
WavelengthList = <float> { <float>, ... }	nm	-	Specifies a list of wavelengths to be used by the extractor for DFT-type simulations.
WavelengthPrecision = <integer>	1	0	Specifies the precision used for matching wavelengths given by WavelengthList and DFT wavelengths resulting from the specification in the DFT section. It also controls the number of digits after the decimal point displayed in the wavelength-identifying part of the extractor file name.

Table 20 Keywords of Extractor section

Keyword	Unit	Default value [range]	Description
WavelengthRange = { <float>, <float> }	nm	-	Specifies the wavelength range to be used by the extractor for DFT-type simulations given by an interval (<min_wavelength>, <max_wavelength>).

Farfield

This section is optional and can occur multiple times.

Table 21 Keywords of Farfield section

Keyword	Unit	Default value [range]	Description
ArraySize = { <integer>, <integer> }	1	{ 1 1 }	Number of times the near-field domain is replicated in each coordinate direction of the 2D plane of the near field.
AzimuthalCutList = <float> { <float>, ... }	deg	-	Defines an explicit list of azimuthal angles. For each angle, an xy plot with constant azimuthal angle is created, whose x-axis denotes the polar angle and the y-axis denotes the far-field intensity. The list is in the format {AzimuthalAngle1, AzimuthalAngle2, ...}.
AzimuthalCutRange = { <float>, <float>, <float> }	deg	-	Defines a list of azimuthal angles. For each angle, an xy plot with constant azimuthal angle is created, whose x-axis denotes the polar angle and the y-axis denotes the far-field intensity. The list is in the format {MinAzimuthalAngle, MaxAzimuthalAngle, AzimuthalAngleStep}.
AzimuthalRange = { <float>, <float>, <float> }	deg	{ 0 360 1 }	Range and discretization of azimuthal angles used for far-field computation. The list is in the format {MinAzimuthalAngle, MaxAzimuthalAngle, AzimuthalAngleStep}.
BoxCorner1 = { <float> min max, <float> min max, <float> min max }	μm	-	One of the two corners of a box defining the near field to be used for the far-field computation. The specified box must be a plane in the 3D simulation domain. Use min or max for the minimum or maximum device extents along the corresponding coordinate axis.

A: Commands
Farfield

Table 21 Keywords of Farfield section

Keyword	Unit	Default value [range]	Description
BoxCorner2 = { <float> min max, <float> min max, <float> min max }	μm	-	One of the two corners of a box defining the near field to be used for the far-field computation. The specified box must be a plane in the 3D simulation domain. Use min or max for the minimum or maximum device extents along the corresponding coordinate axis.
IntegrationRange = { <float>, <float>, <float>, <float>, <float>, <float> } { { <float>, <float>, <float>, <float>, <float>, <float> }, ... }	deg	-	Specifies a list of integration ranges and their discretization for computing the power integration. Each element of the list is in the format of {MinAzimuthalAngle, MaxAzimuthalAngle, AzimuthalAngleStep, MinPolarAngle, MaxPolarAngle, PolarAngleStep}. Note that the total power is always computed, and the corresponding integration range does not have to be specified explicitly.
Name = "<string>"	l	-	Defines the name of the far field, which also is used for the output file name by appending _eml.tdr.
PolarCutList = <float> { <float>, ... }	deg	-	Defines an explicit list of polar angles. For each angle, an xy plot with constant polar angle is created, whose x-axis denotes the azimuthal angle and the y-axis denotes the far-field intensity. The list is in the format {PolarAngle1, PolarAngle2, ...}.
PolarCutRange = { <float>, <float>, <float> }	deg	-	Defines a list of polar angles. For each angle, an xy plot with constant polar angle is created whose x-axis denotes the azimuthal angle and the y-axis denotes the far-field intensity. The list is in the format {MinPolarAngle, MaxPolarAngle, PolarAngleStep}.
PolarRange = { <float>, <float>, <float> }	deg	{ 0 90 1 }	Range and discretization of polar angles used for far-field computation. The list is in the format {MinPolarAngle, MaxPolarAngle, PolarAngleStep}.
Radius = <float>	μm	1000	Radius (distance) at which the far field is calculated.
Region = "<string>"	l	-	Near-field region to be used for the far-field computation. The specified region must be a plane in the 3D simulation domain.
WavelengthList = <float> { <float>, ... }	nm	-	Specifies a list of wavelengths to be used by the far field for DFT-type simulations.

Table 21 Keywords of Farfield section

Keyword	Unit	Default value [range]	Description
WavelengthPrecision = <integer>	1	0	Specifies the precision used for matching wavelengths given by WavelengthList and DFT wavelengths resulting from the specification in the DFT section. It also controls the number of digits after the decimal point displayed in the wavelength-identifying part of the far-field file name.
WavelengthRange = { <float>, <float> }	nm	-	Specifies the wavelength range to be used by the far field for DFT-type simulations given by an interval (<min_wavelength>, <max_wavelength>).

GaussianBeamExcitation

This section is optional and can occur only once.

Table 22 Keywords of GaussianBeamExcitation section

Keyword	Unit	Default value [range]	Description
Amplitude = <float>	V m ⁻¹	1	Signal amplitude.
BeamCenter = { <float>, <float>, <float> }	μm	-	Coordinates of the center (focus) of the Gaussian beam.
BeamPower = <float>	W	2.08478e-15	Signal power of the Gaussian beam.
BeamRadius = <float>	μm	1	Radius (waist) of the Gaussian beam.
BoxCorner1 = { <float> min max, <float> min max, <float> min max }	μm	-	One of the two corners of a box that specifies the excitation plane. Use min or max for the minimum or maximum device extents along the corresponding coordinate axis.
BoxCorner2 = { <float> min max, <float> min max, <float> min max }	μm	-	One of the two corners of a box that specifies the excitation plane. Use min or max for the minimum or maximum device extents along the corresponding coordinate axis.
Delay = <float>	1	0	Number of signal periods before signal starts.
EllipticalPolarizationMagnitude = <float>	1	0	Polarization ratio magnitude.
EllipticalPolarizationPhase = <float>	deg	0	Polarization ratio phase.

A: Commands
GaussianBeamExcitation

Table 22 Keywords of GaussianBeamExcitation section

Keyword	Unit	Default value [range]	Description
Frequency = <float>	s ⁻¹	-	Signal frequency.
Intensity = <float>	W cm ⁻²	1.32721e-07	Signal intensity.
NRise = <float>	1	2	Number of signal periods before full amplitude is reached.
Phi = <float>	deg	0	Azimuth angle of incidence.
PlaneX = <float> <identifier>	μm	-	Excitation line (in two dimensions) or plane (in three dimensions) perpendicular to the x-axis. For <identifier>, use either min or max for the minimum or maximum device extents along the corresponding coordinate axis.
PlaneY = <float> <identifier>	μm	-	Excitation line (in two dimensions) or plane (in three dimensions) perpendicular to the y-axis. For <identifier>, use either min or max for the minimum or maximum device extents along the corresponding coordinate axis.
PlaneZ = <float> <identifier>	μm	-	Excitation plane in three dimensions perpendicular to the z-axis. For <identifier>, use either min or max for the minimum or maximum device extents along the corresponding coordinate axis.
Polarization = <float> <identifier>	1	0.5	Polarization, either TE or TM, or a value between 0 and 1.
PolarizationAngle = <float>	deg	45	Polarization angle.
Psi = <float>	deg	45	Polarization angle.
Region = "<string>"	1	-	Box that specifies the excitation plane.
Sigma = <float>	1	1	Width of transient Gaussian pulse in terms of number of signal periods.
Signal = <identifier>	1	Harmonic	Sets the transient form of the signal. Exclusive options are: <ul style="list-style-type: none"> • Gauss • Harmonic
Theta = <float>	deg	180	Polar angle of incidence.
Wavelength = <float>	nm	-	Signal wavelength.

Globals

This section is mandatory and must occur only once.

Table 23 Keywords of Globals section

Keyword	Unit	Default value [range]	Description
CompressTDR = <identifier>	1	No	Controls whether output TDR files are compressed beyond the basic compression level. Exclusive options are: <ul style="list-style-type: none"> • Yes • No
CRIMIPath = "<string>"	1	.	Search path for shared objects used by complex refractive index model interface.
DomainDecomposition = <identifier>	1	Automatic	Overrides automatic MPI domain decomposition. Used to enforce domain decomposition in only one Cartesian direction. Exclusive options are: <ul style="list-style-type: none"> • Automatic • X • Y • Z
FieldDataFile = "<string>"	1	-	Data file containing datasets, for example, spatial temperature profile, on which the complex refractive index depends.
GridFile = "<string>"	1	-	Tensor grid file for the simulation.
LoadFile = "<string>"	1	-	Name of the results file to be loaded for postprocessing.
LogFile = "<string>"	1	-	Name of the log file. By default, the name of the command file is used with the extension .log. If the name ends with .Z or .gz, a compressed log file will be written.
NumberOfThreads = <integer> <identifier>	1	1	Number of threads to be used for shared-memory parallelization. Either NumberOfThreads = maximum or NumberOfThreads = <integer greater than zero>.
OutputFilePrefix = "<string>"	1	" "	String to be prepended to all output file names including the log file.
OverSampling = <float>	1	1	Reduces the calculated maximum stable time step by the OverSampling factor.

A: Commands
Globals

Table 23 Keywords of Globals section

Keyword	Unit	Default value [range]	Description
ParallelLicenses = identifier { <identifier>, ... }	1	{ MPI SMP }	List of allowed licenses to be used by EMW when run in parallel mode. The default value for simulations started with emw -mpi is ParallelLicenses = {MPI}. Exclusive options are: <ul style="list-style-type: none"> • MPI • SMP
ParameterFile = "<string>"	1	-	Specifies the material parameter file.
ResultFile = "<string>"	1	result_eml.plt	Name of result file.
TdrNativeTensorGridUnit = <identifier>	1	Automatic	Overrides automatic detection of length unit in input tensor grid. Its use may be necessary for tensor grids in [μm] with very small cell sizes or for tensor grids in [m] with very large cell sizes. Exclusive options are: <ul style="list-style-type: none"> • Automatic • m • um
Temperature = <float>	K	300	Global device temperature.
TimeStep = <float>	s	-	Overwrites calculated simulation time step.
TotalSimulationTime = <float>	s	+inf	Maximum simulation time after which the simulation is terminated.
TotalTimeSteps = <integer>	1	+inf	Maximum number of time steps to be performed.
UnavailableLicenseAction = <identifier>	1	serial	Action to be taken when requested license is not available. The default value for simulations started with emw -mpi is abort. Exclusive options are: <ul style="list-style-type: none"> • serial • reduce • wait • abort

Monitor

This section is optional and can occur multiple times.

Table 24 Keywords of Monitor section

Keyword	Unit	Default value [range]	Description
EndTick = <integer>	1	+inf	Specifies the end of the active tick step interval.
EndTime = <float>	s	+inf	Specifies the end of the active time interval.
Frequency = <float>	s ⁻¹	-	Monitor frequency. The default value is calculated from the excitation wavelength.
Location = { <float>, <float>, <float> } { { <float>, <float>, <float> }, ... }	μm	-	Locations to monitor.
Name = "<string>"	1	-	Defines the name of the monitor, which also is used in the dataset name in the result file.
Quantity = <identifier> { <identifier>, ... }	1	{ AbsElectricField }	Specifies the quantities to monitor. Exclusive options are: <ul style="list-style-type: none"> AbsElectricField CplxEMField CplxElectricField RealElectricField RealElectricFieldX RealElectricFieldY RealElectricFieldZ ImagElectricField ImagElectricFieldX ImagElectricFieldY ImagElectricFieldZ AbsMagneticField CplxMagneticField RealMagneticField RealMagneticFieldX RealMagneticFieldY RealMagneticFieldZ ImagMagneticField ImagMagneticFieldX ImagMagneticFieldY ImagMagneticFieldZ
StartTick = <integer>	1	0	Specifies the beginning of the active tick step interval.
StartTime = <float>	s	0	Specifies the beginning of the active time interval.

Table 24 Keywords of Monitor section

Keyword	Unit	Default value [range]	Description
TickStep = <integer>	1	-	Monitoring is performed every <integer> tick step only.
WavelengthList = <float> { <float>, ... }	nm	-	Specifies a list of wavelengths to be used by the monitor for DFT-type simulations.
WavelengthPrecision = <integer>	1	0	Specifies the precision used for matching wavelengths given by WavelengthList and DFT wavelengths resulting from the specification in the DFT section. It also controls the number of digits after the decimal point displayed in the wavelength-identifying part of the monitor name in the result file.
WavelengthRange = { <float>, <float> }	nm	-	Specifies the wavelength range to be used by the plot for DFT-type simulations given by an interval (<min_wavelength>, <max_wavelength>).

PECMedia

This section is optional and can occur multiple times.

Table 25 Keywords of PECMedia section

Keyword	Unit	Default value [range]	Description
ExcludeMaterial = "<string>" { "<string>", ... }	1	-	Names of materials to which PEC medium specification does not apply.
ExcludeRegion = "<string>" { "<string>", ... }	1	-	Names of regions to which PEC medium specification does not apply.
Material = "<string>" { "<string>", ... }	1	-	Names of materials to which the PEC medium specification applies.
Region = "<string>" { "<string>", ... }	1	-	Names of regions to which the PEC medium specification applies.

PlaneWaveExcitation

This section is optional and can occur only once.

Table 26 Keywords of PlaneWaveExcitation section

Keyword	Unit	Default value [range]	Description
Amplitude = <float>	V m ⁻¹	1	Signal amplitude.
BoxCorner1 = { <float> min max, <float> min max, <float> min max }	μm	-	One of the two corners of a box that specifies the excitation plane. Use min or max for the minimum or maximum device extents along the corresponding coordinate axis.
BoxCorner2 = { <float> min max, <float> min max, <float> min max }	μm	-	One of the two corners of a box that specifies the excitation plane. Use min or max for the minimum or maximum device extents along the corresponding coordinate axis.
Delay = <float>	1	0	Number of signal periods before signal starts.
EllipticalPolarizationMagnitude = <float>	1	0	Polarization ratio magnitude.
EllipticalPolarizationPhase = <float>	deg	0	Polarization ratio phase.
Frequency = <float>	s ⁻¹	-	Signal frequency.
Intensity = <float>	W cm ⁻²	1.32721e-07	Signal intensity.
NRise = <float>	1	2	Number of signal periods before full amplitude is reached.
NumberOfPlaneWaves = <integer>	1	1	Number of excitation plane waves.
NumericalAperture = <float>	1	0	Numerical aperture.
PartialCoherenceFactor = <float>	1	1	Partial coherence factor.
Phi = <float>	deg	0	Azimuth angle of incidence.
PlaneX = <float> <identifier>	μm	-	Excitation line (in two dimensions) or plane (in three dimensions) perpendicular to the x-axis. For <identifier>, use either min or max for the minimum or maximum device extents along the corresponding coordinate axis.

A: Commands
PlaneWaveExcitation

Table 26 Keywords of PlaneWaveExcitation section

Keyword	Unit	Default value [range]	Description
PlaneY = <float> <identifier>	μm	-	Excitation line (in two dimensions) or plane (in three dimensions) perpendicular to the y-axis. For <identifier>, use either min or max for the minimum or maximum device extents along the corresponding coordinate axis.
PlaneZ = <float> <identifier>	μm	-	Excitation plane in three dimensions perpendicular to the z-axis. For <identifier>, use either min or max for the minimum or maximum device extents along the corresponding coordinate axis.
Polarization = <float> <identifier>	1	0.5	Polarization, either TE or TM, or a value between 0 and 1.
PolarizationAngle = <float>	deg	45	Polarization angle.
Psi = <float>	deg	45	Polarization angle.
Region = "<string>"	1	-	Box that specifies the excitation plane.
Sigma = <float>	1	1	Width of transient Gaussian pulse in terms of number of signal periods.
Signal = <identifier>	1	Harmonic	Sets the transient form of the signal. Exclusive options are: <ul style="list-style-type: none"> • Gauss • Harmonic
Theta = <float>	deg	180	Polar angle of incidence.
Wavelength = <float>	nm	-	Signal wavelength.

Plot

This section is optional and can occur multiple times.

Table 27 Keywords of Plot section

Keyword	Unit	Default value [range]	Description
BoxCorner1 = { <float> min max, <float> min max, <float> min max }	μm	-	One of the two corners of a box for which data must be plotted. Use min or max for the minimum or maximum device extents along the corresponding coordinate axis.
BoxCorner2 = { <float> min max, <float> min max, <float> min max }	μm	-	One of the two corners of a box for which data must be plotted. Use min or max for the minimum or maximum device extents along the corresponding coordinate axis.
Domain = <identifier>	1	Volume	Specifies whether the values for the volume or only for the surface will be plotted. In the latter case, the sidewalls can be selected with Sides. Exclusive options are: <ul style="list-style-type: none"> • Surface • Volume
EndTick = <integer>	1	+inf	Specifies the end of the active tick step interval.
EndTime = <float>	s	+inf	Specifies the end of the active time interval.
FinalPlot = <identifier>	1	Yes	Controls whether at the end of the simulation a final plot is created. Exclusive options are: <ul style="list-style-type: none"> • Yes • No
GridFile = "<string>"	1	-	Name of mixed-element grid file for output data.
Interpolation = <identifier>	1	Standard	Method of interpolating plot data from the tensor grid to the mixed-element grid. Exclusive options are: <ul style="list-style-type: none"> • Standard • Simple • Conservative
Name = "<string>"	1	-	Defines the name of the plot, which also is used for the output file name by appending <code>_eml.tdr</code> .
PlaneX = <float> <identifier>	μm	-	Plot domain specified as a line (in two dimensions) or a plane (in three dimensions) perpendicular to the x-axis. For <identifier>, use either min or max for the minimum or maximum device extents along the corresponding coordinate axis.

A: Commands
Plot

Table 27 Keywords of Plot section

Keyword	Unit	Default value [range]	Description
PlaneY = <float> <identifier>	μm	-	Plot domain specified as a line (in two dimensions) or a plane (in three dimensions) perpendicular to the y-axis. For <identifier>, use either min or max for the minimum or maximum device extents along the corresponding coordinate axis.
PlaneZ = <float> <identifier>	μm	-	Plot domain specified as a plane in three dimensions perpendicular to the z-axis. For <identifier>, use either min or max for the minimum or maximum device extents along the corresponding coordinate axis.
Quantity = <identifier> { <identifier>, ... }	1	{ AbsElectricField }	Sets the list of quantities to be plotted. Exclusive options are: <ul style="list-style-type: none"> • AbsElectricDisplacement • AbsElectricField • CplxEMField • CplxElectricField • RealElectricField • RealElectricFieldX • RealElectricFieldY • RealElectricFieldZ • ImagElectricField • ImagElectricFieldX • ImagElectricFieldY • ImagElectricFieldZ • AbsMagneticField • CplxMagneticField • RealMagneticField • RealMagneticFieldX • RealMagneticFieldY • RealMagneticFieldZ • ImagMagneticField • ImagMagneticFieldX • ImagMagneticFieldY • ImagMagneticFieldZ • AbsMagneticInduction • ConductionCurrentDensity • ElectricConductivityXX • ElectricConductivityYY • ElectricConductivityZZ • MagneticConductivityXX • MagneticConductivityYY • MagneticConductivityZZ

Table 27 Keywords of Plot section

Keyword	Unit	Default value [range]	Description
Quantity = <identifier> { <identifier>, ... }	1	{ AbsElectric Field }	<ul style="list-style-type: none"> • RelativePermeabilityXX • RelativePermeabilityYY • RelativePermeabilityZZ • RelativePermittivityXX • RelativePermittivityYY • RelativePermittivityZZ • cplxRefIndex • CplxRefIndexXX • CplxRefIndexYY • CplxRefIndexZZ • cplxExtCoeff • CplxExtCoeffXX • CplxExtCoeffYY • CplxExtCoeffZZ • IncoherentRealEx • IncoherentRealEy • IncoherentRealEz • IncoherentRealHx • IncoherentRealHy • IncoherentRealHz • IncoherentImagEx • IncoherentImagEy • IncoherentImagEz • IncoherentImagHx • IncoherentImagHy • IncoherentImagHz • IncoherentIntensity • IncoherentOpticalGeneration • IncoherentAbsorbedPhotonDensity • Region
Region = "<string>" { "<string>", ... }	1	-	Regions for which data must be plotted. If not specified, the whole simulation domain will be plotted.
ScatteredFieldOnly = <identifier>	1	No	Specifies whether the plot involves only scattered fields. Exclusive options are: <ul style="list-style-type: none"> • Yes • No

A: Commands
Plot

Table 27 Keywords of Plot section

Keyword	Unit	Default value [range]	Description
Sides = <identifier> { <identifier>, ... }	l	{ All }	When Domain = Surface, Sides defines the sidewall where plotting will be performed. Exclusive options are: <ul style="list-style-type: none"> • All • X • Xmin • Xmax • Y • Ymin • Ymax • Z • Zmin • Zmax
StartTick = <integer>	l	+inf	Specifies the beginning of the active tick step interval.
StartTime = <float>	s	+inf	Specifies the beginning of the active time interval.
TickStep = <integer>	l	100	Plotting is performed every <integer> tick step only.
WavelengthList = <float> { <float>, ... }	nm	-	Specifies a list of wavelengths to be used by the plot for DFT-type simulations.
WavelengthPrecision = <integer>	l	0	Specifies the precision used for matching wavelengths given by WavelengthList and DFT wavelengths resulting from the specification in the DFT section. It also controls the number of digits after the decimal point displayed in the wavelength-identifying part of the plot file name.
WavelengthRange = { <float>, <float> }	nm	-	Specifies the wavelength range to be used by the plot for DFT-type simulations given by an interval (<min_wavelength>, <max_wavelength>).
WriteBehavior = <identifier>	l	Numbered	Controls how consecutive plot instances are written to file. Exclusive options are: <ul style="list-style-type: none"> • Numbered • Overwrite • OverwriteAndNumbered Use Numbered to include a counter in the file name, which increases with each plot instance. Use Overwrite to have consecutive plot instances overwrite the same file. Use OverwriteAndNumbered to constantly overwrite a file containing the latest plot as well as to have a collection of all plots in separate files distinguished by a counter in the file name.

PMCMedia

This section is optional and can occur multiple times.

Table 28 Keywords of PMCMedia section

Keyword	Unit	Default value [range]	Description
ExcludeMaterial = " <code><string></code> " { " <code><string></code> ", ... }	1	-	Names of materials to which PMC medium specification does not apply.
ExcludeRegion = " <code><string></code> " { " <code><string></code> ", ... }	1	-	Names of regions to which PMC medium specification does not apply.
Material = " <code><string></code> " { " <code><string></code> ", ... }	1	-	Names of materials to which the PMC medium specification applies.
Region = " <code><string></code> " { " <code><string></code> ", ... }	1	-	Names of regions to which the PMC medium specification applies.

Save

This section is optional and can occur multiple times.

Table 29 Keywords of Save section

Keyword	Unit	Default value [range]	Description
BoxCorner1 = { <code><float></code> min max, <code><float></code> min max, <code><float></code> min max }	μm	-	One of the two corners of a box for which data must be saved. Use min or max for the minimum or maximum device extents along the corresponding coordinate axis.
BoxCorner2 = { <code><float></code> min max, <code><float></code> min max, <code><float></code> min max }	μm	-	One of the two corners of a box for which data must be saved. Use min or max for the minimum or maximum device extents along the corresponding coordinate axis.
Name = " <code><string></code> "	1	-	Defines the name of the Save section, which also is used for the output file name by appending <code>_eml.tdr</code> .

A: Commands

Save

Table 29 Keywords of Save section

Keyword	Unit	Default value [range]	Description
Quantity = <identifier> { <identifier>, ... }	1	-	Specifies the quantities to extract. Exclusive options are: <ul style="list-style-type: none"> AbsorbedPhotonDensity IncoherentAbsorbedPhotonDensity PowerFluxDensity CplxEMField CplxElectricField RealElectricField RealElectricFieldX RealElectricFieldY RealElectricFieldZ ImagElectricField ImagElectricFieldX ImagElectricFieldY ImagElectricFieldZ CplxMagneticField RealMagneticField RealMagneticFieldX RealMagneticFieldY RealMagneticFieldZ ImagMagneticField ImagMagneticFieldX ImagMagneticFieldY ImagMagneticFieldZ
Region = "<string>" { "<string>", ... }	1	-	Regions for which data must be saved. If not specified, data for the whole simulation domain will be saved.
WavelengthList = <float> { <float>, ... }	nm	-	Specifies a list of wavelengths to be used by the Save section for DFT-type simulations.
WavelengthPrecision = <integer>	1	0	Specifies the precision used for matching wavelengths given by WavelengthList and DFT wavelengths resulting from the specification in the DFT section. It also controls the number of digits after the decimal point displayed in the wavelength-identifying part of the save file name.
WavelengthRange = { <float>, <float> }	nm	-	Specifies the wavelength range to be used by the Save section for DFT-type simulations given by an interval (<min_wavelength>, <max_wavelength>).

Sensor

This section is optional and can occur multiple times.

Table 30 Keywords of Sensor section

Keyword	Unit	Default value [range]	Description
BoxCenter = { <float>, <float>, <float> }	μm	-	Center of a nonaxis-aligned box.
BoxCorner1 = { <float> min max, <float> min max, <float> min max }	μm	-	One of the two corners of a box that specifies the sensor domain. Use min or max for the minimum or maximum device extents along the corresponding coordinate axis.
BoxCorner2 = { <float> min max, <float> min max, <float> min max }	μm	-	One of the two corners of a box that specifies the sensor domain. Use min or max for the minimum or maximum device extents along the corresponding coordinate axis.
BoxDimensions = { <float>, <float>, <float> }	μm	-	Dimensions of a nonaxis-aligned box.
CoordinateTransformation = <identifier>	1	Unified	Type of coordinate transformation. Exclusive options are: <ul style="list-style-type: none"> Standard Unified
Domains = <identifier>	1	Separate	Set operation on volumes defined by region and box corners for absorption and optical generation. Exclusive options are: <ul style="list-style-type: none"> United Intersecting Separate
EndTick = <integer>	1	+inf	Specifies the end of the active tick step interval.
EndTime = <float>	s	+inf	Specifies the end of the active time interval.
Frequency = <float>	s^{-1}	-	Sensor frequency. The default value is calculated from the excitation wavelength.
Material = "<string>" { "<string>", ... }	1	-	Materials to which sensor applies. If neither Material nor Region is specified, data for the whole simulation domain is used.
Mode = <identifier> { <identifier>, ... }	1	{ Integrate Average }	Integrate integrates a quantity over a surface or in a volume. Average divides the integrated value by the volume or surface area. Exclusive options are: <ul style="list-style-type: none"> Integrate Average

A: Commands
Sensor

Table 30 Keywords of Sensor section

Keyword	Unit	Default value [range]	Description
Name = "<string>"	1	-	Defines the name of the sensor, which also is used in the dataset name in the result file.
PlaneX = <float> <identifier>	μm	-	Sensor domain specified as a line (in two dimensions) or a plane (in three dimensions) perpendicular to the x-axis. For <identifier>, use either min or max for the minimum or maximum device extents along the corresponding coordinate axis.
PlaneY = <float> <identifier>	μm	-	Sensor domain specified as a line (in two dimensions) or a plane (in three dimensions) perpendicular to the y-axis. For <identifier>, use either min or max for the minimum or maximum device extents along the corresponding coordinate axis.
PlaneZ = <float> <identifier>	μm	-	Sensor domain specified as a plane in three dimensions perpendicular to the z-axis. For <identifier>, use either min or max for the minimum or maximum device extents along the corresponding coordinate axis.
Quantity = <identifier>	1	-	Specifies the integration quantity. Fluxes are integrated over surfaces; all others are integrated over volume. Exclusive options are: <ul style="list-style-type: none"> AbsorbedPhotonDensity AbsorbedPowerDensity OpticalGeneration PowerFluxDensity PhotonFluxDensity IncoherentAbsorbedPhotonDensity IncoherentOpticalGeneration
Region = "<string>" { "<string>", ... }	1	-	Regions to which sensor applies. If neither Region nor Material is specified, data for the whole simulation domain is used.
RotationAngles = { <float>, <float>, <float> }	deg	{ 0 90 0 }	Rotation angles (theta, phi, psi) of a nonaxis-aligned box.
ScatteredFieldOnly = <identifier>	1	No	Specifies whether the sensor involves only scattered fields. Exclusive options are: <ul style="list-style-type: none"> Yes No

Table 30 Keywords of Sensor section

Keyword	Unit	Default value [range]	Description
Sides = <identifier> { <identifier>, ... }	1	{ All }	If the quantity is a flux, specifies the sides for which integration is performed. Exclusive options are: <ul style="list-style-type: none"> • All • X • Xmin • Xmax • Y • Ymin • Ymax • Z • Zmin • Zmax
StartTick = <integer>	1	+inf	Specifies the beginning of the active tick step interval.
StartTime = <float>	s	+inf	Specifies the beginning of the active time interval.
TickStep = <integer>	1	-	Sensing is performed every <integer> tick step only.
WavelengthList = <float> { <float>, ... }	nm	-	Specifies a list of wavelengths to be used by the sensor for DFT-type simulations.
WavelengthPrecision = <integer>	1	0	Specifies the precision used for matching wavelengths given by WavelengthList and DFT wavelengths resulting from the specification in the DFT section.
WavelengthRange = { <float>, <float> }	nm	-	Specifies the wavelength range to be used by the sensor for DFT-type simulations given by an interval (<min_wavelength>, <max_wavelength>).

A: Commands

TruncatedPlaneWaveExcitation

TruncatedPlaneWaveExcitation

This section is optional and can occur only once.

Table 31 Keywords of TruncatedPlaneWaveExcitation section

Keyword	Unit	Default value [range]	Description
Amplitude = <float>	V m ⁻¹	1	Signal amplitude.
BoxCorner1 = { <float> min max, <float> min max, <float> min max }	μm	-	One of the two corners of a box that specifies the excitation plane. Use min or max for the minimum or maximum device extents along the corresponding coordinate axis.
BoxCorner2 = { <float> min max, <float> min max, <float> min max }	μm	-	One of the two corners of a box that specifies the excitation plane. Use min or max for the minimum or maximum device extents along the corresponding coordinate axis.
Delay = <float>	1	0	Number of signal periods before signal starts.
EllipticalPolarizationMagnitude = <float>	1	0	Polarization ratio magnitude.
EllipticalPolarizationPhase = <float>	deg	0	Polarization ratio phase.
Frequency = <float>	s ⁻¹	-	Signal frequency.
Intensity = <float>	W cm ⁻²	1.32721e-07	Signal intensity.
NRise = <float>	1	2	Number of signal periods before full amplitude is reached.
NumberOfPlaneWaves = <integer>	1	1	Number of excitation plane waves.
NumericalAperture = <float>	1	0	Numerical aperture.
PartialCoherenceFactor = <float>	1	1	Partial coherence factor.
Phi = <float>	deg	0	Azimuth angle of incidence.
PlaneX = <float> <identifier>	μm	-	Excitation line (in two dimensions) or plane (in three dimensions) perpendicular to the x-axis. For <identifier>, use either min or max for the minimum or maximum device extents along the corresponding coordinate axis.

Table 31 Keywords of TruncatedPlaneWaveExcitation section

Keyword	Unit	Default value [range]	Description
PlaneY = <float> <identifier>	μm	-	Excitation line (in two dimensions) or plane (in three dimensions) perpendicular to the y-axis. For <identifier>, use either min or max for the minimum or maximum device extents along the corresponding coordinate axis.
PlaneZ = <float> <identifier>	μm	-	Excitation plane in three dimensions perpendicular to the z-axis. For <identifier>, use either min or max for the minimum or maximum device extents along the corresponding coordinate axis.
Polarization = <float> <identifier>	1	0.5	Polarization, either TE or TM, or a value between 0 and 1.
PolarizationAngle = <float>	deg	45	Polarization angle.
Psi = <float>	deg	45	Polarization angle.
Region = "<string>"	1	-	Box that specifies the excitation plane.
Sigma = <float>	1	1	Width of transient Gaussian pulse in terms of number of signal periods.
Signal = <identifier>	1	Harmonic	Sets the transient form of the signal. Exclusive options are: <ul style="list-style-type: none"> • Gauss • Harmonic
Theta = <float>	deg	180	Polar angle of incidence.
Wavelength = <float>	nm	-	Signal wavelength.

A: Commands

TruncatedPlaneWaveExcitation

APPENDIX B Troubleshooting Simulations

This appendix provides troubleshooting help for Sentaurus Device Electromagnetic Wave Solver (EMW) simulations.

During simulations, EMW displays the most important issues in standard output. In Sentaurus Workbench, this is the *.out file. In addition, EMW writes a more detailed report to the log file set in the Globals section with LogFile, by default <commandfilename>.log.

The next sections discuss problems that could arise during simulations.

Unexpected Results

Did the simulation converge?

If the simulation converged successfully, you should see the following line in the .out file:

```
Detector: Termination criterion met after 809 steps.
```

Is the excitation correct?

You can double-check the excitation angle in the .out file:

```
Excitation angles in 3d specification: Theta = 90 deg, Phi = 90 deg,  
Psi = 0.0000e+00 deg.  
Excitation angles in 2d specification: Theta = 0.0000e+00 deg,  
Psi = 0.0000e+00 deg.
```

Are the material parameters correct?

In the log file, you can check all values for the refractive index and extinction coefficient:

```
Setting parameters for region "substrate".  
-----  
Complex refractive index: n = 3.939, k = 0.019767
```

Simulations Run Nonstop

Did the simulation converge?

If the simulation converged successfully, you should see the following line in the .out file:

```
Detector: Termination criterion met after 809 steps.
```

Is the value of the time step reasonable?

In the .out file, you can find the chosen time step:

```
Time step set to 3.2810e-17s.
```

It is typically in the range $1e-18$ s – $1e-17$ s. If it is much shorter, you probably have a very short edge of the mesh. Refer to the *Sentaurus™ Mesh User Guide*.

The maximum deviation first decreases but then increases again. What can I do?

You can:

1. From the log file, extract the time steps when the deviation starts to increase.
2. Perform some plotting around this time step to see where the problem is located.
3. Very often, the wave front hits a certain structure or boundary. If it is an absorbing boundary, try to improve the absorption by following the instructions in [Specifying Parameters of CPML Boundary Condition on page 21](#).

Simulator Terminates

If EMW terminates:

1. Check the .out file for error messages.
2. Remove freshly added features, or try to reduce your command file as much as possible, for example, remove all Plot, Extractor, Detector, Sensor, and Save sections.

APPENDIX C Message Passing Interface

This appendix provides frequently asked questions about the message passing interface (MPI) as well as troubleshooting assistance.

Frequently Asked Questions

Can I Run EMW MPI Through Sentaurus Workbench?

Yes, you can. Specify the following command-line option for EMW:

```
$ emw -mpi -n <#processes> -f <hostfile>
```

NOTE The information in [Configuring SSH on page 94](#), [Creating the MPICH Host File on page 95](#), and [Automated Cluster Execution Using EMW Command-Line Option on page 95](#) also applies to running EMW MPI through Sentaurus Workbench.

NOTE An MPI simulation started through Sentaurus Workbench can be terminated by explicitly killing one of the `semw` processes.

Troubleshooting MPI

Verifying MPI Setup Is Correct

The following steps help to verify that the MPI setup is correct:

1. Ensure that the location of MPICH installed with TCAD Sentaurus is in your `$PATH`, before any other MPI implementations, by executing `which mpiexec.hydra`.

Your path can be set in bash using:

```
$ export PATH=$STROOT/tcad/current/linux64/mpich/bin:${PATH}
```

Your path can be set in csh using:

```
$ setenv PATH $STROOT/tcad/current/linux64/mpich/bin:${PATH}
```

C: Message Passing Interface

Troubleshooting MPI

2. Check that you can run a command multiple times on the local node:

```
$ mpiexec.hydra -n 10 hostname
```

3. If this succeeds, you can run EMW MPI with multiple workers on one node, which is useful on a multicore node:

```
$ mpiexec.hydra -n 8 emw <command file>
```

4. Ensure that all hosts mentioned in <hostfile> can run EMW MPI properly. Execute a command on all nodes specified in the <hostfile>:

```
$ mpiexec.hydra -f <hostfile> hostname
```

If the command hangs or generates error messages, locate the cause by subsequent removal of host names from <hostfile>, and then return to Step 2 on that particular host.

5. Start EMW MPI on the nodes specified in the <hostfile>:

```
$ mpiexec.hydra -n <#processes> -f <hostfile> emw <command file>
```

If all previous commands are executed successfully, the system should be set up correctly to run EMW MPI on a cluster.

Glossary

This glossary contains the most frequently used terms applicable to Sentaurus Device Electromagnetic Wave Solver (EMW).

A

ADD

Automatic domain decomposition.

ADE

Auxiliary differential equation.

B

BC

Boundary condition.

C

CFL

Courant–Friedrichs–Lewy.

CPML

Convolutional perfectly matching layer.

CRI

Complex refractive index.

CRIMI

Complex refractive index model interface.

D

DFT

Discrete Fourier transform.

DP

Distributed processing.

E

EMW MPI

The distributed processing mode of EMW.

F

FDTD

Finite-difference time-domain.

L

LSF

Load Sharing Facility.

M

MPD

Management process or daemon.

MPI

Message passing interface.

N

NaN

Not a number.

P

PEC

Perfect electric conductor.

PMC

Perfect magnetic conductor.

Q

QSC

Qualified system configuration. The Synopsys Platforms Core Team defines and communicates the standard system configurations for the build and release environment for all Synopsys products. The environment is documented as the QSC and is part of the corresponding foundation.

S

SMP

Shared-memory parallelization.

T

TFSF

Total-field scattered-field.

Glossary

T